



RTEMS Filesystem Design Guide

Release 6.a3cfaea (25th October 2024)

© 1988, 2024 RTEMS Project and contributors

CONTENTS

1	Preface	3
2	Pathname Evaluation	5
2.1	Pathname Evaluation Handlers	6
2.2	Crossing a Mount Point During Path Evaluation	7
2.3	The <code>rtms_filesystem_location_info_t</code> Structure	8
3	System Initialization	9
3.1	Base Filesystem	10
3.1.1	Base Filesystem Mounting	10
4	Mounting and Unmounting Filesystems	11
4.1	Mount Points	12
4.2	Mount Table Chain	13
4.3	Adding entries to the chain during mount	15
4.4	Removing entries from the chain during unmount	16
5	System Call Development Notes	17
5.1	<code>access</code>	19
5.2	<code>chdir</code>	20
5.3	<code>chmod</code>	21
5.4	<code>chown</code>	22
5.5	<code>close</code>	23
5.6	<code>closedir</code>	24
5.7	<code>dup()</code> Unimplemented	25
5.8	<code>dup2()</code> Unimplemented	26
5.9	<code>fchmod</code>	27
5.10	<code>fcntl()</code>	28
5.11	<code>fdatasync</code>	29
5.12	<code>fpathconf</code>	30
5.13	<code>fstat</code>	32
5.14	<code>ioctl</code>	33
5.15	<code>link</code>	34
5.16	<code>lseek</code>	35
5.17	<code>mkdir</code>	36
5.18	<code>mkfifo</code>	37
5.19	<code>mknod</code>	38
5.20	<code>mount</code>	39

5.21	open	41
5.22	opendir	42
5.23	pathconf	43
5.24	read	44
5.25	readdir	45
5.26	umount	46
5.27	eval	47
5.28	getdentsc	48
6	Filesystem Implementation Requirements	49
6.1	General	50
6.2	File and Directory Removal Constraints	51
6.3	API Layering	52
6.3.1	Mapping of Generic System Calls to Filesystem Specific Functions	52
6.3.2	File/Device/Directory function access via file control block - rtems_libio_t structure	53
6.3.3	File/Directory function access via rtems_filesystem_location_info_t structure	54
6.4	Operation Tables	55
6.4.1	Filesystem Handler Table Functions	55
6.4.1.1	evalpath Handler	55
6.4.1.2	evalformake Handler	56
6.4.1.3	link Handler	56
6.4.1.4	unlink Handler	57
6.4.1.5	node_type Handler	57
6.4.1.6	mknod Handler	57
6.4.1.7	rmnod Handler	57
6.4.1.8	chown Handler	58
6.4.1.9	freenod Handler	58
6.4.1.10	mount Handler	58
6.4.1.11	fsmount_me Handler	59
6.4.1.12	umount Handler	60
6.4.1.13	fsunmount_me Handler	61
6.4.1.14	utime Handler	61
6.4.1.15	eval_link Handler	61
6.4.1.16	symlink Handler	61
6.4.2	File Handler Table Functions	62
6.4.2.1	open Handler	62
6.4.2.1.1	close Handler	62
6.4.2.1.2	read Handler	63
6.4.2.1.3	write Handler	63
6.4.2.1.4	ioctl Handler	63
6.4.2.1.5	lseek Handler	64
6.4.2.1.6	fstat Handler	64
6.4.2.1.7	fchmod Handler	65
6.4.2.1.8	ftruncate Handler	65
6.4.2.1.9	fpathconf Handler	65
6.4.2.1.10	fsync Handler	66
6.4.2.1.11	fdatasync Handler	66
6.4.2.1.12	fcntl Handler	66
7	In-Memory Filesystem	67

7.1	IMFS Per Node Data Structure	68
7.2	Miscellaneous IMFS Information	70
7.3	Memory associated with the IMFS	71
7.3.1	Node removal constraints for the IMFS	71
7.3.2	IMFS General Housekeeping Notes	71
7.4	IMFS Operation Tables	72
7.4.1	IMFS Filesystem Handler Table Functions	72
7.4.1.1	IMFS_evalpath()	72
7.4.1.2	IMFS_evalformake()	73
7.4.1.3	IMFS_link()	73
7.4.1.4	IMFS_unlink()	74
7.4.1.5	IMFS_node_type()	74
7.4.1.6	IMFS_mknod()	74
7.4.1.7	IMFS_rmnod()	75
7.4.1.8	IMFS_chown()	75
7.4.1.9	IMFS_freenod()	76
7.4.1.10	IMFS_freenodinfo()	76
7.4.1.11	IMFS_mount()	76
7.4.1.12	IMFS_fsmount_me()	77
7.4.1.13	IMFS_unmount()	79
7.4.1.14	IMFS_fsunmount()	79
7.4.1.15	IMFS_utime()	79
7.4.1.16	IMFS_eval_link()	80
7.4.2	Regular File Handler Table Functions	80
7.4.2.1	memfile_open() for Regular Files	80
7.4.2.2	memfile_close() for Regular Files	81
7.4.2.3	memfile_read() for Regular Files	81
7.4.2.4	memfile_write() for Regular Files	82
7.4.2.5	memfile_ioctl() for Regular Files	82
7.4.2.6	memfile_lseek() for Regular Files	82
7.4.2.7	IMFS_stat() for Regular Files	83
7.4.2.8	IMFS_fchmod() for Regular Files	84
7.4.2.9	memfile_ftruncate() for Regular Files	84
7.4.2.10	No pathconf() for Regular Files	84
7.4.2.11	No fsync() for Regular Files	85
7.4.2.12	IMFS_fdatasync() for Regular Files	85
7.4.3	Directory Handler Table Functions	85
7.4.3.1	IMFS_dir_open() for Directories	86
7.4.3.2	IMFS_dir_close() for Directories	86
7.4.3.3	IMFS_dir_read() for Directories	87
7.4.3.4	No write() for Directories	87
7.4.3.5	No ioctl() for Directories	87
7.4.3.6	IMFS_dir_lseek() for Directories	88
7.4.3.7	IMFS_dir_fstat() for Directories	88
7.4.3.8	IMFS_fchmod() for Directories	89
7.4.3.9	No ftruncate() for Directories	89
7.4.3.10	No fpathconf() for Directories	90
7.4.3.11	No fsync() for Directories	90
7.4.3.12	IMFS_fdatasync() for Directories	90
7.4.4	Device Handler Table Functions	90
7.4.4.1	device_open() for Devices	91

7.4.4.2	device_close() for Devices	91
7.4.4.3	device_read() for Devices	92
7.4.4.4	device_write() for Devices	92
7.4.4.5	device_ioctl() for Devices	93
7.4.4.6	device_lseek() for Devices	93
7.4.4.7	IMFS_stat() for Devices	94
7.4.4.8	IMFS_fchmod() for Devices	94
7.4.4.9	No ftruncate() for Devices	95
7.4.4.10	No fpathconf() for Devices	95
7.4.4.11	No fsync() for Devices	95
7.4.4.12	No fdatasync() for Devices	96
8	Miniature In-Memory Filesystem	97
9	Trivial FTP Client Filesystem	99
9.1	RTEMS TFTP Filesystem Implementation	100
9.2	Prerequisites	101
9.2.1	RTEMS Tools	101
9.2.2	RTEMS Board Support Package	101
9.2.3	RTEMS libbsd	101
9.2.4	RTEMS Configuration	101
9.2.5	Application Linkage	102
9.2.6	Network Configuration and TFTP Server	103
9.2.7	External TFTP Server Example for OpenSUSE	103
9.3	Usage	104
9.3.1	Mounting the TFTP Filesystem	104
9.3.2	Opening a File	106
9.3.3	Closing a File	106
9.4	Use From Shell	107
9.5	TFTP Client API	108
9.6	Software Design	109
9.6.1	Test Suite	109
10	Command and Variable Index	111

Copyrights and License

© 1988, 2015 On-Line Applications Research Corporation (OAR)

© 2022 embedded brains GmbH & Co. KG

This document is available under the [Creative Commons Attribution-ShareAlike 4.0 International Public License](https://creativecommons.org/licenses/by-sa/4.0/).

The authors have used their best efforts in preparing this material. These efforts include the development, research, and testing of the theories and programs to determine their effectiveness. No warranty of any kind, expressed or implied, with regard to the software or the material contained in this document is provided. No liability arising out of the application or use of any product described in this document is assumed. The authors reserve the right to revise this material and to make changes from time to time in the content hereof without obligation to notify anyone of such revision or changes.

The RTEMS Project is hosted at <https://www.rtems.org>. Any inquiries concerning RTEMS, its related support components, or its documentation should be directed to the RTEMS Project community.

RTEMS Online Resources

Home	https://www.rtems.org
Documentation	https://docs.rtems.org
Mailing Lists	https://lists.rtems.org
Bug Reporting	https://gitlab.rtems.org
Git Repositories	https://gitlab.rtems.org
Developers	https://gitlab.rtems.org

PREFACE

This document describes the implementation of the RTEMS filesystem infrastructure. This infrastructure supports the following capabilities:

- Mountable file systems
- Hierarchical file system directory structure
- POSIX compliant set of routines for the manipulation of files and directories
- Individual file and directory support for the following:
 1. Permissions for read, write and execute
 2. User ID
 3. Group ID
 4. Access time
 5. Modification time
 6. Creation time
- Hard links to files and directories
- Symbolic links to files and directories

This has been implemented to provide the framework for a UNIX-like file system support. POSIX file and directory functions have been implemented that allow a standard method of accessing file, device and directory information within file systems. The file system concept that has been implemented allows for expansion and adaptation of the file system to a variety of existing and future data storage devices. To this end, file system mount and unmount capabilities have been included in this RTEMS framework.

This framework slightly alters the manner in which devices are handled under RTEMS from that of public release 4.0.0 and earlier. Devices that are defined under a given RTEMS configuration will now be registered as files in a mounted file system. Access to these device drivers and their associated devices may now be performed through the traditional file system `open()`, `read()`, `write()`, `lseek()`, `fstat()` and `ioctl()` functions in addition to the interface provided by the IO Manager in the RTEMS Classic API.

An In-Memory File System (IMFS) is included which provides full POSIX filesystem functionality yet is RAM based. The IMFS maintains a node structure for each file, device, and directory in each mounted instantiation of its file system. The node structure is used to manage ownership, access rights, access time, modification time, and creation time. A union of structures within the IMFS nodal structure provide for manipulation of file data, device selection, or directory content

as required by the nodal type. Manipulation of these properties is accomplished through the POSIX set of file and directory functions. In addition to being useful in its own right, the IMFS serves as a full featured example filesystem.

The intended audience for this document is those persons implementing their own filesystem. Users of the filesystem may find information on the implementation useful. But the user interface to the filesystem is through the ISO/ANSI C Library and POSIX 1003.1b file and directory APIs.

PATHNAME EVALUATION

This chapter describes the pathname evaluation process for the RTEMS Filesystem Infrastructure.

1 XXX Include graphic of the path evaluation process

2.1 Pathname Evaluation Handlers

There are two pathname evaluation routines. The handler `patheval()` is called to find, verify privileges on and return information on a node that exists. The handler `evalformake()` is called to find, verify permissions, and return information on a node that is to become a parent. Additionally, `evalformake()` returns a pointer to the start of the name of the new node to be created.

Pathname evaluation is specific to a filesystem. Each filesystem is required to provide both a `patheval()` and an `evalformake()` routine. Both of these routines gets a name to evaluate and a node indicating where to start the evaluation.

2.2 Crossing a Mount Point During Path Evaluation

If the filesystem supports the mount command, the evaluate routines must handle crossing the mountpoint. The evaluate routine should evaluate the name upto the first directory node where the new filesystem is mounted. The filesystem may process terminator characters prior to calling the evaluate routine for the new filesystem. A pointer to the portion of the name which has not been evaluated along with the root node of the new file system (gotten from the mount table entry) is passed to the correct mounted filesystem evaluate routine.

2.3 The `rtems_filesystem_location_info_t` Structure

The `rtems_filesystem_location_info_t` structure contains all information necessary for identification of a node.

The generic rtems filesystem code defines two global `rtems_filesystem_location_info_t` structures, the `rtems_filesystem_root` and the `rtems_filesystem_current`. Both are initially defined to be the root node of the base filesystem. Once the `chdir` command is correctly used the `rtems_filesystem_current` is set to the location specified by the command.

The filesystem generic code peeks at the first character in the name to be evaluated. If this character is a valid separator, the `rtems_filesystem_root` is used as the node to start the evaluation with. Otherwise, the `rtems_filesystem_current` node is used as the node to start evaluating with. Therefore, a valid `rtems_filesystem_location_info_t` is given to the evaluate routine to start evaluation with. The evaluate routines are then responsible for making any changes necessary to this structure to correspond to the name being parsed.

```

1 struct rtems_filesystem_location_info_t {
2     void *node_access;
3     rtems_filesystem_file_handlers_r *handlers;
4     rtems_filesystem_operations_table *ops;
5     rtems_filesystem_mount_table_entry_t *mt_entry;
6 };

```

node_access

This element is filesystem specific. A filesystem can define and store any information necessary to identify a node at this location. This element is normally filled in by the filesystem's evaluate routine. For the filesystem's root node, the filesystem's initialization routine should fill this in, and it should remain valid until the instance of the filesystem is unmounted.

handlers

This element is defined as a set of routines that may change within a given filesystem based upon node type. For example a directory and a memory file may have to completely different read routines. This element is set to an initialization state defined by the mount table, and may be set to the desired state by the evaluation routines.

ops

This element is defined as a set of routines that remain static for the filesystem. This element identifies entry points into the filesystem to the generic code.

mt_entry

This element identifies the mount table entry for this instance of the filesystem.

SYSTEM INITIALIZATION

After the RTEMS initialization is performed, the application's initialization will be performed. Part of initialization is a call to `rtems_filesystem_initialize()`. This routine will mount the 'In Memory File System' as the base filesystem. Mounting the base filesystem consists of the following:

- Initialization of mount table chain control structure
- Allocation of a `jnode` structure that will server as the root node of the 'In Memory Filesystem'
- Initialization of the allocated `jnode` with the appropriate OPS, directory handlers and `pathconf` limits and options.
- Allocation of a memory region for filesystem specific global management variables
- Creation of first mount table entry for the base filesystem
- Initialization of the first mount table chain entry to indicate that the mount point is NULL and the mounted filesystem is the base file system

After the base filesystem has been mounted, the following operations are performed under its directory structure:

- Creation of the `/dev` directory
- Registration of devices under `/dev` directory

3.1 Base Filesystem

RTEMS initially mounts a RAM based file system known as the base file system. The root directory of this file system tree serves as the logical root of the directory hierarchy (Figure 3). Under the root directory a '/dev' directory is created under which all I/O device directories and files are registered as part of the file system hierarchy.

1 Figure of the tree structure goes here.

A RAM based file system draws its management resources from memory. File and directory nodes are simply allocated blocks of memory. Data associated with regular files is stored in collections of memory blocks. When the system is turned off or restarted all memory-based components of the file system are lost.

The base file system serves as a starting point for the mounting of file systems that are resident on semi-permanent storage media. Examples of such media include non-volatile memory, flash memory and IDE hard disk drives (Figure 3). File systems of other types will be mounted onto mount points within the base file system or other file systems that are subordinate to the base file system. The framework set up under the base file system will allow for these new file system types and the unique data and functionality that is required to manage the future file systems.

3.1.1 Base Filesystem Mounting

At present, the first file system to be mounted is the 'In Memory File System'. It is mounted using a standard MOUNT() command in which the mount point is NULL. This flags the mount as the first file system to be registered under the operating system and appropriate initialization of file system management information is performed (See figures 4 and 5). If a different file system type is desired as the base file system, alterations must be made to base_fs.c. This routine handles the mount of the base file system.

1 Figure of the mount table chain goes here.

Once the root of the base file system has been established and it has been recorded as the mount point of the base file system, devices are integrated into the base file system. For every device that is configured into the system (See ioman.c) a device registration process is performed. Device registration produces a unique dev_t handle that consists of a major and minor device number. In addition, the configuration information for each device contains a text string that represents the fully qualified pathname to that device's place in the base file system's hierarchy. A file system node is created for the device along the specified registration path.

1 Figure of the Mount Table Processing goes here.

Note: Other file systems can be mounted but they are mounted onto points (directory mount points) in the base file system.

MOUNTING AND UNMOUNTING FILESYSTEMS

4.1 Mount Points

The following is the list of the characteristics of a mount point:

- The mount point must be a directory. It may have files and other directories under it. These files and directories will be hidden when the filesystem is mounted.
- The task must have read/write/execute permissions to the mount point or the mount attempt will be rejected.
- Only one filesystem can be mounted to a single mount point.
- The Root of the mountable filesystem will be referenced by the name of the mount point after the mount is complete.

4.2 Mount Table Chain

The mount table chain is a dynamic list of structures that describe mounted filesystems a specific points in the filesystem hierarchy. It is initialized to an empty state during the base filesystem initialization. The mount operation will add entries to the mount table chain. The un-mount operation will remove entries from the mount table chain.

Each entry in the mount table chain is of the following type:

```

1 struct rtems_filesystem_mount_table_entry_tt
2 {
3     Chain_Node                Node;
4     rtems_filesystem_location_info_t  mt_point_node;
5     rtems_filesystem_location_info_t  mt_fs_root;
6     int                       options;
7     void                       *fs_info;
8     rtems_filesystem_limits_and_options_t pathconf_limits_and_options;
9     /*
10    * When someone adds a mounted filesystem on a real device,
11    * this will need to be used.
12    *
13    * The best option long term for this is probably an
14    * open file descriptor.
15    */
16     char                       *dev;
17 };

```

Node

The Node is used to produce a linked list of mount table entry nodes.

mt_point_node

The `mt_point_node` contains all information necessary to access the directory where a filesystem is mounted onto. This element may contain memory that is allocated during a path evaluation of the filesystem containing the mountpoint directory. The generic code allows this memory to be returned by unmount when the filesystem identified by `mt_fs_root` is unmounted.

mt_fs_root

The `mt_fs_root` contains all information necessary to identify the root of the mounted filesystem. The user is never allowed access to this node by the generic code, but it is used to identify to the mounted filesystem where to start evaluation of pathnames at.

options

XXX

fs_info

The `fs_info` element is a location available for use by the mounted file system to identify unique things applicable to this instance of the file system. For example the IMFS uses this space to provide node identification that is unique for each instance (mounting) of the filesystem.

pathconf_limits_and_options

XXX

dev

This character string represents the device where the filesystem will reside.

4.3 Adding entries to the chain during mount

When a filesystem is mounted, its presence and location in the file system hierarchy is recorded in a dynamic list structure known as a chain. A unique `rtems_filesystem_mount_table_entry_tt` structure is logged for each filesystem that is mounted. This includes the base filesystem.

4.4 Removing entries from the chain during unmount

When a filesystem is dismounted its entry in the mount table chain is extracted and the memory for this entry is freed.

SYSTEM CALL DEVELOPMENT NOTES

This set of routines represents the application's interface to files and directories under the RTEMS filesystem. All routines are compliant with POSIX standards if a specific interface has been established. The list below represents the routines that have been included as part of the application's interface.

1. `access()`
2. `chdir()`
3. `chmod()`
4. `chown()`
5. `close()`
6. `closedir()`
7. `dup()`
8. `dup2()`
9. `fchmod()`
10. `fcntl()`
11. `fdatasync()`
12. `fpathconf()`
13. `fstat()`
14. `ioctl()`
15. `link()`
16. `lseek()`
17. `mkdir()`
18. `mkfifo()`
19. `mknod()`
20. `mount()`
21. `open()`
22. `opendir()`
23. `pathconf()`

- 24. read()
- 25. readdir()
- 26. unmount()

The sections that follow provide developmental information concerning each of these functions.

5.1 access

File:

access.c

Processing:

This routine is layered on the `stat()` function. It acquires the current status information for the specified file and then determines if the caller has the ability to access the file for read, write or execute according to the mode argument to this function.

Development Comments:

This routine is layered on top of the `stat()` function. As long as the `st_mode` element in the returned structure follow the standard UNIX conventions, this function should support other filesystems without alteration.

5.2 chdir

File:

chdir.c

Processing:

This routine will determine if the pathname that we are attempting to make that current directory exists and is in fact a directory. If these conditions are met the global indication of the current directory (`rtems_filesystem_current`) is set to the `rtems_filesystem_location_info_t` structure that is returned by the `rtems_filesystem_evaluate_path()` routine.

Development Comments:

This routine is layered on the `rtems_filesystem_evaluate_path()` routine and the filesystem specific OP table function `node_type()`.

The routine `node_type()` must be a routine provided for each filesystem since it must access the filesystems node information to determine which of the following types the node is:

- `RTEMS_FILESYSTEM_DIRECTORY`
- `RTEMS_FILESYSTEM_DEVICE`
- `RTEMS_FILESYSTEM_HARD_LINK`
- `RTEMS_FILESYSTEM_MEMORY_FILE`

This acknowledges that the form of the node management information can vary from one filesystem implementation to another.

RTEMS has a special global structure that maintains the current directory location. This global variable is of type `rtems_filesystem_location_info_t` and is called `rtems_filesystem_current`. This structure is not always valid. In order to determine if the structure is valid, you must first test the `node_access` element of this structure. If the pointer is `NULL`, then the structure does not contain a valid indication of what the current directory is.

5.3 chmod

File:

chmod.c

Processing:

This routine is layered on the `open()`, `fchmod()` and `close()` functions. As long as the standard interpretation of the `mode_t` value is maintained, this routine should not need modification to support other filesystems.

Development Comments:

The routine first determines if the selected file can be open with read/write access. This is required to allow modification of the mode associated with the selected path.

The `fchmod()` function is used to actually change the mode of the path using the integer file descriptor returned by the `open()` function.

After mode modification, the open file descriptor is closed.

5.4 chown

File:

chown.c

Processing:

This routine is layered on the `rtems_filesystem_evaluate_path()` and the file system specific `chown()` routine that is specified in the OPS table for the file system.

Development Comments:

`rtems_filesystem_evaluate_path()` is used to determine if the path specified actually exists. If it does a `rtems_filesystem_location_info_t` structure will be obtained that allows the shell function to locate the OPS table that is to be used for this filesystem.

It is possible that the `chown()` function that should be in the OPS table is not defined. A test for a non-NULL OPS table `chown()` entry is performed before the function is called.

If the `chown()` function is defined in the indicated OPS table, the function is called with the `rtems_filesystem_location_info_t` structure returned from the path evaluation routine, the desired owner, and group information.

5.5 close

File:

close.c

Processing:

This routine will allow for the closing of both network connections and file system devices. If the file descriptor is associated with a network device, the appropriate network function handler will be selected from a table of previously registered network functions (`rtems_libio_handlers`) and that function will be invoked.

If the file descriptor refers to an entry in the filesystem, the appropriate handler will be selected using information that has been placed in the file control block for the device (`rtems_libio_t` structure).

Development Comments:

`rtems_file_descriptor_type` examines some of the upper bits of the file descriptor index. If it finds that the upper bits are set in the file descriptor index, the device referenced is a network device.

Network device handlers are obtained from a special registration table (`rtems_libio_handlers`) that is set up during network initialization. The network handler invoked and the status of the network handler will be returned to the calling process.

If none of the upper bits are set in the file descriptor index, the file descriptor refers to an element of the RTEMS filesystem.

The following sequence will be performed for any filesystem file descriptor:

1. Use the `rtems_libio_iop()` function to obtain the `rtems_libio_t` structure for the file descriptor
2. Range check the file descriptor using `rtems_libio_check_fd()`
3. Determine if there is actually a function in the selected handler table that processes the `close()` operation for the filesystem and node type selected. This is generally done to avoid execution attempts on functions that have not been implemented.
4. If the function has been defined it is invoked with the file control block pointer as its argument.
5. The file control block that was associated with the open file descriptor is marked as free using `rtems_libio_free()`.
6. The return code from the close handler is then passed back to the calling program.

5.6 closedir

File:

`closedir.c`

Processing:

The code was obtained from the BSD group. This routine must clean up the memory resources that are required to track an open directory. The code is layered on the `close()` function and standard memory `free()` functions. It should not require alterations to support other filesystems.

Development Comments:

The routine alters the file descriptor and the index into the DIR structure to make it an invalid file descriptor. Apparently the memory that is about to be freed may still be referenced before it is reallocated.

The `dd_buf` structure's memory is reallocated before the control structure that contains the pointer to the `dd_buf` region.

DIR control memory is reallocated.

The `close()` function is used to free the file descriptor index.

5.7 dup() Unimplemented

File:

dup.c

Processing:

Development Comments:

5.8 dup2() Unimplemented

File:

dup2.c

Processing:

Development Comments:

5.9 fchmod

File:

fchmod.c

Processing:

This routine will alter the permissions of a node in a filesystem. It is layered on the following functions and macros:

- rtems_file_descriptor_type()
- rtems_libio_iop()
- rtems_libio_check_fd()
- rtems_libio_check_permissions()
- fchmod() function that is referenced by the handler table in the file control block associated with this file descriptor

Development Comments:

The routine will test to see if the file descriptor index is associated with a network connection. If it is, an error is returned from this routine.

The file descriptor index is used to obtain the associated file control block.

The file descriptor value is range checked.

The file control block is examined to determine if it has write permissions to allow us to alter the mode of the file.

A test is made to determine if the handler table that is referenced in the file control block contains an entry for the fchmod() handler function. If it does not, an error is returned to the calling routine.

If the fchmod() handler function exists, it is called with the file control block and the desired mode as parameters.

5.10 fcntl()

File:

fcntl.c

Processing:

This routine currently only interacts with the file control block. If the structure of the file control block and the associated meanings do not change, the partial implementation of fcntl() should remain unaltered for other filesystem implementations.

Development Comments:

The only commands that have been implemented are the F_GETFD and F_SETFD. The commands manipulate the LIBIO_FLAGS_CLOSE_ON_EXEC bit in the ``flags`` element of the file control block associated with the file descriptor index.

The current implementation of the function performs the sequence of operations below:

1. Test to see if we are trying to operate on a file descriptor associated with a network connection
2. Obtain the file control block that is associated with the file descriptor index
3. Perform a range check on the file descriptor index.

5.11 fdatsync

File:

fdatsync.c

Processing:

This routine is a template in the in memory filesystem that will route us to the appropriate handler function to carry out the fdatsync() processing. In the in memory filesystem this function is not necessary. Its function in a disk based file system that employs a memory cache is to flush all memory based data buffers to disk. It is layered on the following functions and macros:

- rtems_file_descriptor_type()
- rtems_libio_iop()
- rtems_libio_check_fd()
- rtems_libio_check_permissions()
- fdatsync() function that is referenced by the handler table in the file control block associated with this file descriptor

Development Comments:

The routine will test to see if the file descriptor index is associated with a network connection. If it is, an error is returned from this routine.

The file descriptor index is used to obtain the associated file control block.

The file descriptor value is range checked.

The file control block is examined to determine if it has write permissions to the file.

A test is made to determine if the handler table that is referenced in the file control block contains an entry for the fdatsync() handler function. If it does not an error is returned to the calling routine.

If the fdatsync() handler function exists, it is called with the file control block as its parameter.

5.12 fpathconf

File:

fpathconf.c

Processing:

This routine is layered on the following functions and macros:

- rtems_file_descriptor_type()
- rtems_libio_iop()
- rtems_libio_check_fd()
- rtems_libio_check_permissions()

When a filesystem is mounted, a set of constants is specified for the filesystem. These constants are stored with the mount table entry for the filesystem. These constants appear in the POSIX standard and are listed below.

- PCLINKMAX
- PCMAXCANON
- PCMAXINPUT
- PCNAMEMAX
- PCPATHMAX
- PCPIPEBUF
- PCCHOWNRESTRICTED
- PCNOTRUNC
- PCVDSABLE
- PCASYNCIO
- PCPRIOIO
- PCSYNCIO

This routine will find the mount table information associated the file control block for the specified file descriptor parameter. The mount table entry structure contains a set of filesystem specific constants that can be accessed by individual identifiers.

Development Comments:

The routine will test to see if the file descriptor index is associated with a network connection. If it is, an error is returned from this routine.

The file descriptor index is used to obtain the associated file control block.

The file descriptor value is range checked.

The file control block is examined to determine if it has read permissions to the file.

Pathinfo in the file control block is used to locate the mount table entry for the filesystem associated with the file descriptor.

The mount table entry contains the pathconf_limits_and_options element. This element is a table of constants that is associated with the filesystem.

The `name` argument is used to reference the desired constant from the `pathconf_limits_and_options` table.

5.13 fstat

File:

fstat.c

Processing:

This routine will return information concerning a file or network connection. If the file descriptor is associated with a network connection, the current implementation of `fstat()` will return a mode set to `S_IFSOCK`. In a later version, this routine will map the status of a network connection to an external handler routine.

If the file descriptor is associated with a node under a filesystem, the `fstat()` routine will map to the `fstat()` function taken from the node handler table.

Development Comments:

This routine validates that the struct `stat` pointer is not `NULL` so that the return location is valid.

The struct `stat` is then initialized to all zeros.

`rtems_file_descriptor_type()` is then used to determine if the file descriptor is associated with a network connection. If it is, network status processing is performed. In the current implementation, the file descriptor type processing needs to be improved. It currently just drops into the normal processing for file system nodes.

If the file descriptor is associated with a node under a filesystem, the following steps are performed:

1. Obtain the file control block that is associated with the file descriptor index.
2. Range check the file descriptor index.
3. Test to see if there is a non-`NULL` function pointer in the handler table for the `fstat()` function. If there is, invoke the function with the file control block and the pointer to the `stat` structure.

5.14 ioctl

File:

ioctl.c

Processing:

Not defined in the POSIX 1003.1b standard but commonly supported in most UNIX and POSIX system. `ioctl()` is a catchall for I/O operations. Routine is layered on external network handlers and filesystem specific handlers. The development of new filesystems should not alter the basic processing performed by this routine.

Development Comments:

The file descriptor is examined to determine if it is associated with a network device. If it is processing is mapped to an external network handler. The value returned by this handler is then returned to the calling program.

File descriptors that are associated with a filesystem undergo the following processing:

1. The file descriptor index is used to obtain the associated file control block.
2. The file descriptor value is range checked.
3. A test is made to determine if the handler table that is referenced in the file control block contains an entry for the `ioctl()` handler function. If it does not, an error is returned to the calling routine.
4. If the `ioctl()` handler function exists, it is called with the file control block, the command and buffer as its parameters.
5. The return code from this function is then sent to the calling routine.

5.15 link

File:

link.c

Processing:

This routine will establish a hard link to a file, directory or a device. The target of the hard link must be in the same filesystem as the new link being created. A link to an existing link is also permitted but the existing link is evaluated before the new link is made. This implies that links to links are reduced to links to files, directories or devices before they are made.

Development Comments:

Calling parameters:

```
1 const char *existing
2 const char *new
```

link() will determine if the target of the link actually exists using `rtems_filesystem_evaluate_path()`

`rtems_filesystem_get_start_loc()` is used to determine where to start the path evaluation of the new name. This macro examines the first characters of the name to see if the name of the new link starts with a `rtems_filesystem_is_separator`. If it does the search starts from the root of the RTEMS filesystem; otherwise the search will start from the current directory.

The OPS table `evalformake()` function for the parent's filesystem is used to locate the node that will be the parent of the new link. It will also locate the start of the new path's name. This name will be used to define a child under the parent directory.

If the parent is found, the routine will determine if the hard link that we are trying to create will cross a filesystem boundary. This is not permitted for hard-links.

If the hard-link does not cross a filesystem boundary, a check is performed to determine if the OPS table contains an entry for the `link()` function.

If a `link()` function is defined, the OPS table `link()` function will be called to establish the actual link within the filesystem.

The return code from the OPS table `link()` function is returned to the calling program.

5.16 lseek

File:

lseek.c

Processing:

This routine is layered on both external handlers and filesystem / node type specific handlers. This routine should allow for the support of new filesystems without modification.

Development Comments:

This routine will determine if the file descriptor is associated with a network device. If it is lseek will map to an external network handler. The handler will be called with the file descriptor, offset and whence as its calling parameters. The return code from the external handler will be returned to the calling routine.

If the file descriptor is not associated with a network connection, it is associated with a node in a filesystem. The following steps will be performed for filesystem nodes:

1. The file descriptor is used to obtain the file control block for the node.
2. The file descriptor is range checked.
3. The offset element of the file control block is altered as indicated by the offset and whence calling parameters
4. The handler table in the file control block is examined to determine if it contains an entry for the lseek() function. If it does not an error is returned to the calling program.
5. The lseek() function from the designated handler table is called with the file control block, offset and whence as calling arguments
6. The return code from the lseek() handler function is returned to the calling program

5.17 mkdir

File:

mkdir.c

Processing:

This routine attempts to create a directory node under the filesystem. The routine is layered the `mknod()` function.

Development Comments:

See `mknod()` for developmental comments.

5.18 mkfifo

File:

mkfifo.c

Processing:

This routine attempts to create a FIFO node under the filesystem. The routine is layered the `mknod()` function.

Development Comments:

See `mknod()` for developmental comments

5.19 mknod

File:

mknod.c

Processing:

This function will allow for the creation of the following types of nodes under the filesystem:

- directories
- regular files
- character devices
- block devices
- fifos

At the present time, an attempt to create a FIFO will result in an ENOTSUP error to the calling function. This routine is layered the filesystem specific routines evalformake and mknod. The introduction of a new filesystem must include its own evalformake and mknod function to support the generic mknod() function. Under this condition the generic mknod() function should accommodate other filesystem types without alteration.

Development Comments:

Test for nodal types - I thought that this test should look like the following code:

```

1  if ( (mode & S_IFDIR) == S_IFDIR) ||
2      (mode & S_IFREG) == S_IFREG) ||
3      (mode & S_IFCHR) == S_IFCHR) ||
4      (mode & S_IFBLK) == S_IFBLK) ||
5      (mode & S_IFIFO) == S_IFIFO))
6      Set_errno_and_return_minus_one (EINVAL);

```

Where:

- S_IFREG (0100000) - Creation of a regular file
- S_IFCHR (0020000) - Creation of a character device
- S_IFBLK (0060000) - Creation of a block device
- S_IFIFO (0010000) - Creation of a FIFO

Determine if the pathname that we are trying to create starts at the root directory or is relative to the current directory using the rtems_filesystem_get_start_loc() function.

Determine if the pathname leads to a valid directory that can be accessed for the creation of a node.

If the pathname is a valid location to create a node, verify that a filesystem specific mknod() function exists.

If the mknod() function exists, call the filesystem specific mknod() function. Pass the name, mode, device type and the location information associated with the directory under which the node will be created.

5.20 mount

File:

mount.c

Arguments (Not a standard POSIX call):

```
1 rtems_filesystem_mount_table_entry_t **mt_entry,
```

If the mount operation is successful, this pointer to a pointer will be set to reference the mount table chain entry that has been allocated for this file system mount.

```
1 rtems_filesystem_operations_table *fs_ops,
```

This is a pointer to a table of functions that are associated with the file system that we are about to mount. This is the mechanism to selected file system type without keeping a dynamic database of all possible file system types that are valid for the mount operation. Using this method, it is only necessary to configure the filesystems that we wish to use into the RTEMS build. Unused filesystems types will not be drawn into the build.

```
1 char *fsoptions,
```

This argument points to a string that selects mounting for read only access or read/write access. Valid states are “RO” and “RW”

```
1 char *device,
```

This argument is reserved for the name of a device that will be used to access the filesystem information. Current filesystem implementations are memory based and do not require a device to access filesystem information.

```
1 char *mount_point
```

This is a pathname to a directory in a currently mounted filesystem that allows read, write and execute permissions. If successful, the node found by evaluating this name, is stored in the mt_entry.

Processing:

This routine will handle the mounting of a filesystem on a mount point. If the operation is successful, a pointer to the mount table chain entry associated with the mounted filesystem will be returned to the calling function. The specifics about the processing required at the mount point and within the filesystem being mounted is isolated in the filesystem specific mount() and fsmount_me() functions. This allows the generic mount() function to remain unaltered even if new filesystem types are introduced.

Development Comments:

This routine will use get_file_system_options() to determine if the mount options are valid (“RO” or “RW”).

It confirms that a filesystem ops-table has been selected.

Space is allocated for a mount table entry and selective elements of the temporary mount table entry are initialized.

If a mount point is specified: The mount point is examined to determine that it is a directory and also has the appropriate permissions to allow a filesystem to be mounted.

The current mount table chain is searched to determine that there is not another filesystem mounted at the mount point we are trying to mount onto.

If a mount function is defined in the ops table for the filesystem containing the mount point, it is called at this time.

If no mount point is specified: Processing is performed to set up the mount table chain entry as the base filesystem.

If the `fsmount_me()` function is specified for ops-table of the filesystem being mounted, that function is called to initialize for the new filesystem.

On successful completion, the temporary mount table entry will be placed on the mount table chain to record the presence of the mounted filesystem.

5.21 open

File:

open.c

Processing:

This routine is layered on both RTEMS calls and filesystem specific implementations of the `open()` function. These functional interfaces should not change for new filesystems and therefore this code should be stable as new file systems are introduced.

Development Comments:

This routine will allocate a file control block for the file or device that we are about to open.

It will then test to see if the pathname exists. If it does a `rtems_filesystem_location_info_t` data structure will be filled out. This structure contains information that associates node information, filesystem specific functions and mount table chain information with the pathname.

If the create option has been it will attempt to create a node for a regular file along the specified path. If a file already exists along this path, an error will be generated; otherwise, a node will be allocated for the file under the filesystem that contains the pathname. When a new node is created, it is also evaluated so that an appropriate `rtems_filesystem_location_info_t` data structure can be filled out for the newly created node.

If the file exists or the new file was created successfully, the file control block structure will be initialized with handler table information, node information and the `rtems_filesystem_location_info_t` data structure that describes the node and filesystem data in detail.

If an `open()` function exists in the filesystem specific handlers table for the node that we are trying to open, it will be called at this time.

If any error is detected in the process, cleanup is performed. It consists of freeing the file control block structure that was allocated at the beginning of the generic `open()` routine.

On a successful `open()`, the index into the file descriptor table will be calculated and returned to the calling routine.

5.22 opendir

File:

opendir.c

Processing:

This routine will attempt to open a directory for read access. It will setup a DIR control structure that will be used to access directory information. This routine is layered on the generic open() routine and filesystem specific directory processing routines.

Development Comments:

The BSD group provided this routine.

5.23 pathconf

File:

pathconf.c

Processing:

This routine will obtain the value of one of the path configuration parameters and return it to the calling routine. It is layered on the generic `open()` and `fpathconf()` functions. These interfaces should not change with the addition of new filesystem types.

Development Comments:

This routine will try to open the file indicated by path.

If successful, the file descriptor will be used to access the pathconf value specified by name using the `fpathconf()` function.

The file that was accessed is then closed.

5.24 read

File:

deviceio.c

Processing:

This routine is layered on a set of RTEMS calls and filesystem specific read operations. The functions are layered in such a way as to isolate them from change as new filesystems are introduced.

Development Comments:

This routine will examine the type of file descriptor it is sent.

If the file descriptor is associated with a network device, the read function will be mapped to a special network handler. The return code from the network handler will then be sent as the return code from generic read() function.

For file descriptors that are associated with the filesystem the following sequence will be performed:

1. Obtain the file control block associated with the file descriptor
2. Range check the file descriptor
3. Determine that the buffer pointer is not invalid
4. Check that the count is not zero
5. Check the file control block to see if we have permissions to read
6. If there is a read function in the handler table, invoke the handler table read() function
7. Use the return code from the handler table read function(number of bytes read) to increment the offset element of the file control block
8. Return the number of bytes read to the calling program

5.25 readdir

File:

readdir.c

Processing:

This routine was acquired from the BSD group. It has not been altered from its original form.

Development Comments:

The routine calls a customized `getdents()` function that is provided by the user. This routine provides the filesystem specific aspects of reading a directory.

It is layered on the `read()` function in the directory handler table. This function has been mapped to the `Imfs_dir_read()` function.

5.26 unmount

File:

`unmount.c`

Processing:

This routine will attempt to dismount a mounted filesystem and then free all resources that were allocated for the management of that filesystem.

Development Comments:

- This routine will determine if there are any filesystems currently mounted under the filesystem that we are trying to dismount. This would prevent the dismount of the filesystem.
- It will test to see if the current directory is in the filesystem that we are attempting to dismount. This would prevent the dismount of the filesystem.
- It will scan all the currently open file descriptors to determine if there is an open file descriptor to a file in the filesystem that we are attempting to unmount().

If the above preconditions are met then the following sequence is performed:

1. Call the filesystem specific `unmount()` function for the filesystem that contains the mount point. This routine should indicate that the mount point no longer has a filesystem mounted below it.
2. Call the filesystem specific `fsunmount_me()` function for the mounted filesystem that we are trying to unmount(). This routine should clean up any resources that are no longer needed for the management of the file system being un-mounted.
3. Extract the mount table entry for the filesystem that was just dismounted from the mount table chain.
4. Free the memory associated with the extracted mount table entry.

5.27 eval

File:

XXX

Processing:

XXX

Development Comments:

XXX

5.28 getdentsc

File:

XXX

Processing:

XXX

Development Comments:

XXX

FILESYSTEM IMPLEMENTATION REQUIREMENTS

This chapter details the behavioral requirements that all filesystem implementations must adhere to.

6.1 General

The RTEMS filesystem framework was intended to be compliant with the POSIX Files and Directories interface standard. The following filesystem characteristics resulted in a functional switching layer.

- 1 Figure of the Filesystem Functional Layering goes here.
- 2 This figure includes networking and disk caching layering.

- # Application programs are presented with a standard set of POSIX compliant functions** that allow them to interface with the files, devices and directories in the filesystem. The interfaces to these routines do not reflect the type of subordinate filesystem implementation in which the file will be found.
- # The filesystem framework developed under RTEMS allows for mounting filesystem** of different types under the base filesystem.
- # The mechanics of locating file information may be quite different between** filesystem types.
 - # The process of locating a file may require crossing filesystem boundaries.
- # The transitions between filesystem and the processing required to access** information in different filesystem is not visible at the level of the POSIX function call.
- # The POSIX interface standard provides file access by character pathname to** the file in some functions and through an integer file descriptor in other functions.
- # The nature of the integer file descriptor and its associated processing is** operating system and filesystem specific.
- # Directory and device information must be processed with some of the same** routines that apply to files.
- # The form and content of directory and device information differs greatly from** that of a regular file.
- # Files, directories and devices represent elements (nodes) of a tree** hierarchy.
- # The rules for processing each of the node types that exist under the** filesystem are node specific but are still not reflected in the POSIX interface routines.

- 1 Figure of the Filesystem Functional Layering goes here.
- 2 This figure focuses on the Base Filesystem and IMFS.

- 1 Figure of the IMFS Memfile control blocks

6.2 File and Directory Removal Constraints

The following POSIX constraints must be honored by all filesystems.

- If a node is a directory with children it cannot be removed.
- The root node of any filesystem, whether the base filesystem or a mounted filesystem, cannot be removed.
- A node that is a directory that is acting as the mount point of a file system cannot be removed.
- On filesystems supporting hard links, a link count is maintained. Prior to node removal, the node's link count is decremented by one. The link count must be less than one to allow for removal of the node.

6.3 API Layering

6.3.1 Mapping of Generic System Calls to Filesystem Specific Functions

The list of generic system calls includes the routines `open()`, `read()`, `write()`, `close()`, etc..

The Files and Directories section of the POSIX Application Programs Interface specifies a set of functions with calling arguments that are used to gain access to the information in a filesystem. To the application program, these functions allow access to information in any mounted filesystem without explicit knowledge of the filesystem type or the filesystem mount configuration. The following are functions that are provided to the application:

1. `access()`
2. `chdir()`
3. `chmod()`
4. `chown()`
5. `close()`
6. `closedir()`
7. `fchmod()`
8. `fcntl()`
9. `fdatasync()`
10. `fpathconf()`
11. `fstat()`
12. `fsync()`
13. `ftruncate()`
14. `link()`
15. `lseek()`
16. `mkdir()`
17. `mknod()`
18. `mount()`
19. `open()`
20. `opendir()`
21. `pathconf()`
22. `read()`
23. `readdir()`
24. `rewinddir()`
25. `rmdir()`
26. `rmnod()`
27. `scandir()`

28. `seekdir()`
29. `stat()`
30. `telldir()`
31. `umask()`
32. `unlink()`
33. `unmount()`
34. `utime()`
35. `write()`

The filesystem's type as well as the node type within the filesystem determine the nature of the processing that must be performed for each of the functions above. The RTEMS filesystem provides a framework that allows new filesystem to be developed and integrated without alteration to the basic framework.

To provide the functional switching that is required, each of the POSIX file and directory functions have been implemented as a shell function. The shell function adheres to the POSIX interface standard. Within this functional shell, filesystem and node type information is accessed which is then used to invoke the appropriate filesystem and node type specific routine to process the POSIX function call.

6.3.2 File/Device/Directory function access via file control block - `rtems_libio_t` structure

The POSIX `open()` function returns an integer file descriptor that is used as a reference to file control block information for a specific file. The file control block contains information that is used to locate node, file system, mount table and functional handler information. The diagram in Figure 8 depicts the relationship between and among the following components.

File Descriptor Table:

This is an internal RTEMS structure that tracks all currently defined file descriptors in the system. The index that is returned by the file `open()` operation references a slot in this table. The slot contains a pointer to the file descriptor table entry for this file. The `rtems_libio_t` structure represents the file control block.

Allocation of entry in the File Descriptor Table:

Access to the file descriptor table is controlled through a semaphore that is implemented using the `rtems_libio_allocate()` function. This routine will grab a semaphore and then scan the file control blocks to determine which slot is free for use. The first free slot is marked as used and the index to this slot is returned as the file descriptor for the `open()` request. After the alterations have been made to the file control block table, the semaphore is released to allow further operations on the table.

Maximum number of entries in the file descriptor table is configurable through the `src/exec/sapi/headers/confdefs.h` file. If the `CONFIGURE_LIBIO_MAXIMUM_FILE_DESCRIPTOR` constant is defined its value will represent the maximum number of file descriptors that are allowed. If `CONFIGURE_LIBIO_MAXIMUM_FILE_DESCRIPTOR` is not specified a default value of 20 will be used as the maximum number of file descriptors allowed.

File control block - `rtems_libio_t` structure:

```

1 struct rtems_libio_tt {
2     rtems_driver_name_t      *driver;
3     off_t                    size;
4     off_t                    offset;
5     unsigned32               flags;
6     rtems_filesystem_location_info_t pathinfo;
7     Objects_Id               sem;
8     unsigned32               data0;
9     void                     data1;
10    void                     file_info;
11    rtems_filesystem_file_handlers_r handlers;
12 };

```

A file control block can exist for regular files, devices and directories. The following fields are important for regular file and directory access:

- Size - For a file this represents the number of bytes currently stored in a file. For a directory this field is not filled in.
- Offset - For a file this is the byte file position index relative to the start of the file. For a directory this is the byte offset into a sequence of dirent structures.
- Pathinfo - This is a structure that provides a pointer to node information, OPS table functions, Handler functions and the mount table entry associated with this node.
- file_info - A pointer to node information that is used by Handler functions
- handlers - A pointer to a table of handler functions that operate on a file, device or directory through a file descriptor index

6.3.3 File/Directory function access via rtems_filesystem_location_info_t structure

The rtems_filesystem_location_info_tt structure below provides sufficient information to process nodes under a mounted filesystem.

```

1 struct rtems_filesystem_location_info_tt {
2     void                     *node_access;
3     rtems_filesystem_file_handlers_r *handlers;
4     rtems_filesystem_operations_table *ops;
5     rtems_filesystem_mount_table_entry_t *mt_entry;
6 };

```

It contains a void pointer to filesystem specific nodal structure, pointers to the OPS table for the filesystem that contains the node, the node type specific handlers for the node and a reference pointer to the mount table entry associated with the filesystem containing the node

6.4 Operation Tables

Filesystem specific operations are invoked indirectly. The set of routines that implement the filesystem are configured into two tables. The Filesystem Handler Table has routines that are specific to a filesystem but remain constant regardless of the actual file type. The File Handler Table has routines that are both filesystem and file type specific.

6.4.1 Filesystem Handler Table Functions

OPS table functions are defined in a `rtems_filesystem_operations_table` structure. It defines functions that are specific to a given filesystem. One table exists for each filesystem that is supported in the RTEMS configuration. The structure definition appears below and is followed by general developmental information on each of the functions contained in this function management structure.

```

1 typedef struct {
2     rtems_filesystem_evalpath_t      evalpath;
3     rtems_filesystem_evalmake_t     evalformake;
4     rtems_filesystem_link_t         link;
5     rtems_filesystem_unlink_t       unlink;
6     rtems_filesystem_node_type_t    node_type;
7     rtems_filesystem_mknod_t        mknod;
8     rtems_filesystem_rmnod_t        rmnod;
9     rtems_filesystem_chown_t        chown;
10    rtems_filesystem_freenode_t      freenod;
11    rtems_filesystem_mount_t         mount;
12    rtems_filesystem_fsmount_me_t    fsmount_me;
13    rtems_filesystem_unmount_t       unmount;
14    rtems_filesystem_fsunmount_me_t  fsunmount_me;
15    rtems_filesystem_utime_t         utime;
16    rtems_filesystem_evaluate_link_t eval_link;
17    rtems_filesystem_symlink_t       symlink;
18 } rtems_filesystem_operations_table;

```

6.4.1.1 evalpath Handler

Corresponding Structure Element:

`evalpath`

Arguments:

```

1 const char      *pathname,      /* IN */
2 int             flags,          /* IN */
3 rtems_filesystem_location_info_t *pathloc /* IN/OUT */

```

Description:

This routine is responsible for evaluating the pathname passed in based upon the flags and the valid `rtems_filesystem_location_info_t`. Additionally, it must make any changes to

pathloc necessary to identify the pathname node. This should include calling the evalpath for a mounted filesystem, if the given filesystem supports the mount command.

This routine returns a 0 if the evaluation was successful. Otherwise, it returns a -1 and sets errno to the correct error.

This routine is required and should NOT be set to NULL.

6.4.1.2 evalformake Handler

Corresponding Structure Element:

evalformake

Arguments:

```

1 const char          *path,          /* IN */
2 rtems_filesystem_location_info_t *pathloc, /* IN/OUT */
3 const char          **name         /* OUT */

```

Description:

This method is given a path to evaluate and a valid start location. It is responsible for finding the parent node for a requested make command, setting pathloc information to identify the parent node, and setting the name pointer to the first character of the name of the new node. Additionally, if the filesystem supports the mount command, this method should call the evalformake routine for the mounted filesystem.

This routine returns a 0 if the evaluation was successful. Otherwise, it returns a -1 and sets errno to the correct error.

This routine is required and should NOT be set to NULL. However, if the filesystem does not support user creation of a new node, it may set errno to ENOSYS and return -1.

6.4.1.3 link Handler

Corresponding Structure Element:

link

Arguments:

```

1 rtems_filesystem_location_info_t *to_loc,    /* IN */
2 rtems_filesystem_location_info_t *parent_loc, /* IN */
3 const char                      *token     /* IN */

```

Description:

This routine is used to create a hard-link.

It will first examine the st_nlink count of the node that we are trying to. If the link count exceeds LINK_MAX an error will be returned.

The name of the link will be normalized to remove extraneous separators from the end of the name.

This routine is not required and may be set to NULL.

6.4.1.4 unlink Handler

Corresponding Structure Element:

unlink

Arguments:

XXX

Description:

XXX

6.4.1.5 node_type Handler

Corresponding Structure Element:

node_type()

Arguments:

```
1 rtems_filesystem_location_info_t *pathloc /* IN */
```

Description:

XXX

6.4.1.6 mknod Handler

Corresponding Structure Element:

mknod()

Arguments:

```
1 const char *token, /* IN */
2 mode_t mode, /* IN */
3 dev_t dev, /* IN */
4 rtems_filesystem_location_info_t *pathloc /* IN/OUT */
```

Description:

XXX

6.4.1.7 rmnod Handler

Corresponding Structure Element:

rmnod()

Arguments:

XXX

Description:

XXX

6.4.1.8 chown Handler

Corresponding Structure Element:

chown()

Arguments:

1	rtems_filesystem_location_info_t	*pathloc	/* IN */
2	uid_t	owner	/* IN */
3	gid_t	group	/* IN */

Description:

XXX

6.4.1.9 freenod Handler

Corresponding Structure Element:

freenod()

Arguments:

1	rtems_filesystem_location_info_t	*pathloc	/* IN */
---	----------------------------------	----------	----------

Description:

This routine is used by the generic code to allow memory to be allocated during the evaluate routines, and set free when the generic code is finished accessing a node. If the evaluate routines allocate memory to identify a node this routine should be utilized to free that memory.

This routine is not required and may be set to NULL.

6.4.1.10 mount Handler

Corresponding Structure Element:

mount()

Arguments:

1	rtems_filesystem_mount_table_entry_t	*mt_entry
---	--------------------------------------	-----------

Description:

XXX

6.4.1.11 fsmount_me Handler

Corresponding Structure Element:

imfs_fsmount_me

Arguments:

```
1 rtems_filesystem_mount_table_entry_t *mt_entry
```

Description:

This function is provided with a filesystem to take care of the internal filesystem management details associated with mounting that filesystem under the RTEMS environment.

It is not responsible for the mounting details associated the filesystem containing the mount point.

The rtems_filesystem_mount_table_entry_t structure contains the key elements below:

```
1 rtems_filesystem_location_info_t *mt_point_node,
```

This structure contains information about the mount point. This allows us to find the ops-table and the handling functions associated with the filesystem containing the mount point.

```
1 rtems_filesystem_location_info_t *fs_root_node,
```

This structure contains information about the root node in the file system to be mounted. It allows us to find the ops-table and the handling functions associated with the filesystem to be mounted.

```
1
```

```
rtems_filesystem_options_t options,
```

```
Read only or read/write access
```

```
1 void *fs_info,
```

This points to an allocated block of memory the will be used to hold any filesystem specific information of a global nature. This allocated region if important because it allows us to mount the same filesystem type more than once under the RTEMS system. Each instance of the mounted filesystem has its own set of global management information that is separate from the global management information associated with the other instances of the mounted filesystem type.

```
1 rtems_filesystem_limits_and_options_t pathconf_info,
```

The table contains the following set of values associated with the mounted filesystem:

- link_max
- max_canon
- max_input
- name_max

- path_max
- pipe_buf
- posix_async_io
- posix_chown_restrictions
- posix_no_trunc
- posix_prio_io
- posix_sync_io
- posix_vdisable

These values are accessed with the pathconf() and the fpathconf () functions.

```
1 const char *dev
```

The is intended to contain a string that identifies the device that contains the filesystem information. The filesystems that are currently implemented are memory based and don't require a device specification.

If the mt_point_node.node_access is NULL then we are mounting the base file system.

The routine will create a directory node for the root of the IMFS file system.

The node will have read, write and execute permissions for owner, group and others.

The node's name will be a null string.

A filesystem information structure(fs_info) will be allocated and initialized for the IMFS filesystem. The fs_info pointer in the mount table entry will be set to point the filesystem information structure.

The pathconf_info element of the mount table will be set to the appropriate table of path configuration constants (LIMITS_AND_OPTIONS).

The fs_root_node structure will be filled in with the following:

- pointer to the allocated root node of the filesystem
- directory handlers for a directory node under the IMFS filesystem
- OPS table functions for the IMFS

A 0 will be returned to the calling routine if the process succeeded, otherwise a 1 will be returned.

6.4.1.12 unmount Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

6.4.1.13 fsunmount_me Handler

Corresponding Structure Element:

imfs_fsunmount_me()

Arguments:

```
1 rtems_filesystem_mount_table_entry_t *mt_entry
```

Description:

XXX

6.4.1.14 utime Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

6.4.1.15 eval_link Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

6.4.1.16 symlink Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

6.4.2 File Handler Table Functions

Handler table functions are defined in a `rtems_filesystem_file_handlers_r` structure. It defines functions that are specific to a node type in a given filesystem. One table exists for each of the filesystem's node types. The structure definition appears below. It is followed by general developmental information on each of the functions associated with regular files contained in this function management structure.

```

1 typedef struct {
2     rtems_filesystem_open_t      open;
3     rtems_filesystem_close_t    close;
4     rtems_filesystem_read_t     read;
5     rtems_filesystem_write_t    write;
6     rtems_filesystem_ioctl_t    ioctl;
7     rtems_filesystem_lseek_t    lseek;
8     rtems_filesystem_fstat_t    fstat;
9     rtems_filesystem_fchmod_t   fchmod;
10    rtems_filesystem_ftruncate_t ftruncate;
11    rtems_filesystem_fpathconf_t fpathconf;
12    rtems_filesystem_fsync_t     fsync;
13    rtems_filesystem_fdatasync_t fdatasync;
14    rtems_filesystem_fcntl_t     fcntl;
15 } rtems_filesystem_file_handlers_r;

```

6.4.2.1 open Handler

Corresponding Structure Element:

`open()`

Arguments:

```

1 rtems_libio_t *iop,
2 const char   *pathname,
3 unsigned32   flag,
4 unsigned32   mode

```

Description:

XXX

close Handler

Corresponding Structure Element:

`close()`

Arguments:

```

1 rtems_libio_t *iop

```

Description:

XXX

NOTES:

XXX

read Handler

Corresponding Structure Element:

read()

Arguments:

```
1 rtems_libio_t    *iop,  
2 void            *buffer,  
3 unsigned32      count
```

Description:

XXX

NOTES:

XXX

write Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

NOTES:

XXX

ioctl Handler

Corresponding Structure Element:

XXX

Arguments:

```
1 rtems_libio_t    *iop,  
2 unsigned32      command,  
3 void            *buffer
```

Description:

XXX

NOTES:

XXX

lseek Handler

Corresponding Structure Element:

lseek()

Arguments:

```

1 rtems_libio_t      *iop,
2 off_t             offset,
3 int               whence

```

Description:

XXX

NOTES:

XXX

fstat Handler

Corresponding Structure Element:

fstat()

Arguments:

```

1 rtems_filesystem_location_info_t *loc,
2 struct stat                  *buf

```

Description:

The following information is extracted from the filesystem specific node and placed in the stat structure:

- st_mode
- st_nlink
- st_ino
- st_uid
- st_gid
- st_atime
- st_mtime
- st_ctime

NOTES:

Both the stat() and lstat() services are implemented directly using the fstat() handler. The difference in behavior is determined by how the path is evaluated prior to this handler being called on a particular file entity.

The `fstat()` system call is implemented directly on top of this filesystem handler.

fchmod Handler

Corresponding Structure Element:

`fchmod()`

Arguments:

1	<code>rtems_libio_t</code>	<code>*iop</code>
2	<code>mode_t</code>	<code>mode</code>

Description:

XXX

NOTES:

XXX

ftruncate Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

NOTES:

XXX

fpathconf Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

NOTES:

XXX

fsync Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

NOTES:

XXX

fdatasync Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

NOTES:

XXX

fcntl Handler

Corresponding Structure Element:

XXX

Arguments:

XXX

Description:

XXX

NOTES:

XXX

IN-MEMORY FILESYSTEM

This chapter describes the In-Memory FileSystem (IMFS). The IMFS is a full featured POSIX filesystem that keeps all information in memory.

7.1 IMFS Per Node Data Structure

Each regular file, device, hard link, and directory is represented by a data structure called a *jnode*. The *jnode* is formally represented by the structure:

```

1 struct IMFS_jnode_tt {
2     Chain_Node      Node;           /* for chaining them together */
3     IMFS_jnode_t    *Parent;       /* Parent node */
4     char            name[NAME_MAX+1]; /* "basename" */
5     mode_t          st_mode;       /* File mode */
6     nlink_t         st_nlink;      /* Link count */
7     ino_t           st_ino;        /* inode */
8     uid_t           st_uid;        /* User ID of owner */
9     gid_t           st_gid;        /* Group ID of owner */
10    time_t          st_atime;       /* Time of last access */
11    time_t          st_mtime;       /* Time of last modification */
12    time_t          st_ctime;       /* Time of last status change */
13    IMFS_jnode_types_t type;       /* Type of this entry */
14    IMFS_typs_union  info;
15 };

```

The key elements of this structure are listed below together with a brief explanation of their role in the filesystem.

Node

exists to allow the entire *jnode* structure to be included in a chain.

Parent

is a pointer to another *jnode* structure that is the logical parent of the node in which it appears. This field may be NULL if the file associated with this node is deleted but there are open file descriptors on this file or there are still hard links to this node.

name

is the name of this node within the filesystem hierarchical tree. Example: If the fully qualified pathname to the *jnode* was */a/b/c*, the *jnode* name field would contain the null terminated string "c".

st_mode

is the standard Unix access permissions for the file or directory.

st_nlink

is the number of hard links to this file. When a *jnode* is first created its link count is set to 1. A *jnode* and its associated resources cannot be deleted unless its link count is less than 1.

st_ino

is a unique node identification number

st_uid

is the user ID of the file's owner

st_gid

is the group ID of the file's owner

st_atime

is the time of the last access to this file

st_mtime

is the time of the last modification of this file

st_ctime

is the time of the last status change to the file

type

is the indication of node type must be one of the following states:

- IMFS_DIRECTORY
- IMFS_MEMORY_FILE
- IMFS_HARD_LINK
- IMFS_SYM_LINK
- IMFS_DEVICE

info

is this contains a structure that is unique to file type (See IMFS_typs_union in imfs.h).

- IMFS_DIRECTORY

An IMFS directory contains a dynamic chain structure that records all files and directories that are subordinate to the directory node.

- IMFS_MEMORY_FILE

Under the in memory filesystem regular files hold data. Data is dynamically allocated to the file in 128 byte chunks of memory. The individual chunks of memory are tracked by arrays of pointers that record the address of the allocated chunk of memory. Single, double, and triple indirection pointers are used to record the locations of all segments of the file. The memory organization of an IMFS file are discussed elsewhere in this manual.

- IMFS_HARD_LINK

The IMFS filesystem supports the concept of hard links to other nodes in the IMFS filesystem. These hard links are actual pointers to other nodes in the same filesystem. This type of link cannot cross-filesystem boundaries.

- IMFS_SYM_LINK

The IMFS filesystem supports the concept of symbolic links to other nodes in any filesystem. A symbolic link consists of a pointer to a character string that represents the pathname to the target node. This type of link can cross-filesystem boundaries. Just as with most versions of UNIX supporting symbolic links, a symbolic link can point to a non-existent file.

- IMFS_DEVICE

All RTEMS devices now appear as files under the in memory filesystem. On system initialization, all devices are registered as nodes under the file system.

7.2 Miscellaneous IMFS Information

TBD

7.3 Memory associated with the IMFS

A memory based filesystem draws its resources for files and directories from the memory resources of the system. When it is time to un-mount the filesystem, the memory resources that supported filesystem are set free. In order to free these resources, a recursive walk of the filesystems tree structure will be performed. As the leaf nodes under the filesystem are encountered their resources are freed. When directories are made empty by this process, their resources are freed.

7.3.1 Node removal constraints for the IMFS

The IMFS conforms to the general filesystem requirements for node removal. See *File and Directory Removal Constraints* (page 51).

7.3.2 IMFS General Housekeeping Notes

The following is a list of odd housekeeping notes for the IMFS.

- If the global variable `rtems_filesystem_current` refers to the node that we are trying to remove, the `node_access` element of this structure must be set to `NULL` to invalidate it.
- If the node was of `IMFS_MEMORY_FILE` type, free the memory associated with the memory file before freeing the node. Use the `IMFS_memfile_remove()` function.

7.4 IMFS Operation Tables

7.4.1 IMFS Filesystem Handler Table Functions

OPS table functions are defined in a `rtems_filesystem_operations_table` structure. It defines functions that are specific to a given filesystem. One table exists for each filesystem that is supported in the RTEMS configuration. The structure definition appears below and is followed by general developmental information on each of the functions contained in this function management structure.

```
1 rtems_filesystem_operations_table IMFS_ops = {
2     IMFS_eval_path,
3     IMFS_evaluate_for_make,
4     IMFS_link,
5     IMFS_unlink,
6     IMFS_node_type,
7     IMFS_mknod,
8     IMFS_rmnod,
9     IMFS_chown,
10    IMFS_freenodinfo,
11    IMFS_mount,
12    IMFS_initialize,
13    IMFS_unmount,
14    IMFS_fsunmount,
15    IMFS_utime,
16    IMFS_evaluate_link,
17    IMFS_symlink,
18    IMFS_readlink
19 };
```

7.4.1.1 IMFS_evalpath()

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.1.2 IMFS_evalformake()

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.1.3 IMFS_link()

Corresponding Structure Element:

link

Arguments:

```

1 rtems_filesystem_location_info_t *to_loc, /* IN */
2 rtems_filesystem_location_info_t *parent_loc, /* IN */
3 const char *token /* IN */

```

File:

imfs_link.c

Description:

This routine is used in the IMFS filesystem to create a hard-link.

It will first examine the `st_nlink` count of the node that we are trying to. If the link count exceeds `LINK_MAX` an error will be returned.

The name of the link will be normalized to remove extraneous separators from the end of the name.

`IMFS_create_node` will be used to create a filesystem node that will have the following characteristics:

- parent that was determined in the `link()` function in file `link.c`
- Type will be set to `IMFS_HARD_LINK`
- name will be set to the normalized name
- mode of the hard-link will be set to the mode of the target node

If there was trouble allocating memory for the new node an error will be returned.

The `st_nlink` count of the target node will be incremented to reflect the new link.

The time fields of the link will be set to reflect the creation time of the hard-link.

7.4.1.4 IMFS_unlink()

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.1.5 IMFS_node_type()

Corresponding Structure Element:

IMFS_node_type()

Arguments:

```
1 rtems_filesystem_location_info_t *pathloc /* IN */
```

File:

imfs_notype.c

Description:

This routine will locate the IMFS_jnode_t structure that holds ownership information for the selected node in the filesystem.

This structure is pointed to by pathloc->node_access.

The IMFS_jnode_t type element indicates one of the node types listed below:

- RTEMS_FILESYSTEM_DIRECTORY
- RTEMS_FILESYSTEM_DEVICE
- RTEMS_FILESYSTEM_HARD_LINK
- RTEMS_FILESYSTEM_MEMORY_FILE

7.4.1.6 IMFS_mknod()

Corresponding Structure Element:

IMFS_mknod()

Arguments:

```
1 const char *token, /* IN */
2 mode_t mode, /* IN */
3 dev_t dev, /* IN */
4 rtems_filesystem_location_info_t *pathloc /* IN/OUT */
```


File:

imfs_mknod.c

Description:

This routine will examine the mode argument to determine if we are trying to create a directory, regular file and a device node. The creation of other node types is not permitted and will cause an assert.

Memory space will be allocated for a jnode and the node will be set up according to the nodal type that was specified. The IMFS_create_node() function performs the allocation and setup of the node.

The only problem that is currently reported is the lack of memory when we attempt to allocate space for the jnode (ENOMEM).

7.4.1.7 IMFS_rmnod()

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.1.8 IMFS_chown()

Corresponding Structure Element:

IMFS_chown()

Arguments:

1	rtcms_filesystem_location_info_t	*pathloc	/* IN */
2	uid_t	owner	/* IN */
3	gid_t	group	/* IN */

File:

imfs_chown.c

Description:

This routine will locate the IMFS_jnode_t structure that holds ownership information for the selected node in the filesystem.

This structure is pointed to by pathloc->node_access.

The st_uid and st_gid fields of the node are then modified. Since this is a memory based filesystem, no further action is required to alter the ownership of the IMFS_jnode_t structure.

7.4.1.9 IMFS_freenod()

Corresponding Structure Element:

IMFS_freenod()

Arguments:

```
1 rtems_filesystem_location_info_t    *pathloc    /* IN */
```

File:

imfs_free.c

Description:

This method is a private function to the IMFS. It is called by IMFS routines to free nodes that have been allocated. Examples of where this routine may be called from are unlink and rmnod.

Note: This routine should not be confused with the filesystem callback freenod. The IMFS allocates memory until the node no longer exists.

7.4.1.10 IMFS_freenodinfo()

Corresponding Structure Element:

IMFS_freenodinfo()

Arguments:

```
1 rtems_filesystem_location_info_t    *pathloc    /* IN */
```

File:

imfs_free.c

Description:

The In-Memory File System does not need to allocate memory during the evaluate routines. Therefore, this routine simply routines PASS.

7.4.1.11 IMFS_mount()

Corresponding Structure Element:

IMFS_mount()

Arguments:

```
1 rtems_filesystem_mount_table_entry_t *mt_entry
```

File:

imfs_mount.c

Description:

This routine provides the filesystem specific processing required to mount a filesystem for the

system that contains the mount point. It will determine if the point that we are trying to mount onto is a node of `IMFS_DIRECTORY` type.

If it is the node's info element is altered so that the `info.directory.mt_fs` element points to the mount table chain entry that is associated with the mounted filesystem at this point. The `info.directory.mt_fs` element can be examined to determine if a filesystem is mounted at a directory. If it is `NULL`, the directory does not serve as a mount point. A non-`NULL` entry indicates that the directory does serve as a mount point and the value of `info.directory.mt_fs` can be used to locate the mount table chain entry that describes the filesystem mounted at this point.

7.4.1.12 `IMFS_fsmount_me()`

Corresponding Structure Element:

`IMFS_initialize()`

Arguments:

```
1 rtems_filesystem_mount_table_entry_t *mt_entry
```

File:

`imfs_init.c`

Description:

This function is provided with a filesystem to take care of the internal filesystem management details associated with mounting that filesystem under the RTEMS environment.

It is not responsible for the mounting details associated the filesystem containing the mount point.

The `rtems_filesystem_mount_table_entry_t` structure contains the key elements below:

```
1 rtems_filesystem_location_info_t *mt_point_node,
```

This structure contains information about the mount point. This allows us to find the ops-table and the handling functions associated with the filesystem containing the mount point.

```
1 rtems_filesystem_location_info_t *fs_root_node,
```

This structure contains information about the root node in the file system to be mounted. It allows us to find the ops-table and the handling functions associated with the filesystem to be mounted.

```
1 rtems_filesystem_options_t options,
```

Read only or read/write access

```
1 void *fs_info,
```

This points to an allocated block of memory the will be used to hold any filesystem specific information of a global nature. This allocated region if important because it allows us to mount the same filesystem type more than once under the RTEMS system. Each instance of the mounted filesystem has its own set of global management information that is separate

from the global management information associated with the other instances of the mounted filesystem type.

```
1 rtems_filesystem_limits_and_options_t    pathconf_info,
```

The table contains the following set of values associated with the mounted filesystem:

- link_max
- max_canon
- max_input
- name_max
- path_max
- pipe_buf
- posix_async_io
- posix_chown_restrictions
- posix_no_trunc
- posix_prio_io
- posix_sync_io
- posix_vdisable

These values are accessed with the `pathconf()` and the `fpathconf ()` functions.

```
1 const char                               *dev
```

The is intended to contain a string that identifies the device that contains the filesystem information. The filesystems that are currently implemented are memory based and don't require a device specification.

If the `mt_point_node.node_access` is NULL then we are mounting the base file system.

The routine will create a directory node for the root of the IMFS file system.

The node will have read, write and execute permissions for owner, group and others.

The node's name will be a null string.

A filesystem information structure(`fs_info`) will be allocated and initialized for the IMFS filesystem. The `fs_info` pointer in the mount table entry will be set to point the filesystem information structure.

The `pathconf_info` element of the mount table will be set to the appropriate table of path configuration constants (`IMFS_LIMITS_AND_OPTIONS`).

The `fs_root_node` structure will be filled in with the following:

- pointer to the allocated root node of the filesystem
- directory handlers for a directory node under the IMFS filesystem
- OPS table functions for the IMFS

A 0 will be returned to the calling routine if the process succeeded, otherwise a 1 will be returned.

7.4.1.13 IMFS_unmount()

Corresponding Structure Element:

IMFS_unmount()

Arguments:

```
1 rtems_filesystem_mount_table_entry_t *mt_entry
```

File:

imfs_unmount.c

Description:

This routine allows the IMFS to unmount a filesystem that has been mounted onto a IMFS directory.

The mount entry mount point node access is verified to be a mounted directory. Its `mt_fs` is set to `NULL`. This identifies to future calls into the IMFS that this directory node is no longer a mount point. Additionally, it will allow any directories that were hidden by the mounted system to again become visible.

7.4.1.14 IMFS_fsunmount()

Corresponding Structure Element:

imfs_fsunmount()

Arguments:

```
1 rtems_filesystem_mount_table_entry_t *mt_entry
```

File:

imfs_init.c

Description:

This method unmounts this instance of the IMFS file system. It is the counterpart to the `IMFS_initialize` routine. It is called by the generic code under the `fsunmount_me` callback.

All method loops finding the first encountered node with no children and removing the node from the tree, thus returning allocated resources. This is done until all allocated nodes are returned.

7.4.1.15 IMFS_utime()

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.1.16 IMFS_eval_link()

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.2 Regular File Handler Table Functions

Handler table functions are defined in a `rtems_filesystem_file_handlers_r` structure. It defines functions that are specific to a node type in a given filesystem. One table exists for each of the filesystem's node types. The structure definition appears below. It is followed by general developmental information on each of the functions associated with regular files contained in this function management structure.

```

1 rtems_filesystem_file_handlers_r IMFS_memfile_handlers = {
2     memfile_open,
3     memfile_close,
4     memfile_read,
5     memfile_write,
6     memfile_ioctl,
7     memfile_lseek,
8     IMFS_stat,
9     IMFS_fchmod,
10    memfile_ftruncate,
11    NULL,           /* fpathconf */
12    NULL,           /* fsync */
13    IMFS_fdatasync,
14    IMFS_fcntl
15 };

```

7.4.2.1 memfile_open() for Regular Files

Corresponding Structure Element:

memfile_open()

Arguments:

```

1 rtems_libio_t  *iop,
2 const char   *pathname,
3 unsigned32    flag,
4 unsigned32    mode

```

File:

memfile.c

Description:

Currently this function is a shell. No meaningful processing is performed and a success code is always returned.

7.4.2.2 memfile_close() for Regular Files

Corresponding Structure Element:

memfile_close()

Arguments:

```

1 rtems_libio_t  *iop

```

File:

memfile.c

Description:

This routine is a dummy for regular files under the base filesystem. It performs a capture of the IMFS_jnode_t pointer from the file control block and then immediately returns a success status.

7.4.2.3 memfile_read() for Regular Files

Corresponding Structure Element:

memfile_read()

Arguments:

```

1 rtems_libio_t  *iop,
2 void          *buffer,
3 unsigned32    count

```

File:

memfile.c

Description:

This routine will determine the jnode that is associated with this file.

It will then call IMFS_memfile_read() with the jnode, file position index, buffer and transfer count as arguments.

IMFS_memfile_read() will do the following:

- Verify that the jnode is associated with a memory file

- Verify that the destination of the read is valid
- Adjust the length of the read if it is too long
- Acquire data from the memory blocks associated with the file
- Update the access time for the data in the file

7.4.2.4 memfile_write() for Regular Files

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.2.5 memfile_ioctl() for Regular Files

Corresponding Structure Element:

XXX

Arguments:

```

1 rtems_libio_t *iop,
2 unsigned32    command,
3 void          *buffer
```

File:

memfile.c

Description:

The current code is a placeholder for future development. The routine returns a successful completion status.

7.4.2.6 memfile_lseek() for Regular Files

Corresponding Structure Element:

Memfile_lseek()

Arguments:

```

1 rtems_libio_t *iop,
2 off_t         offset,
3 int           whence
```


File:

memfile.c

Description:

This routine make sure that the memory based file is sufficiently large to allow for the new file position index.

The `IMFS_memfile_extend()` function is used to evaluate the current size of the memory file and allocate additional memory blocks if required by the new file position index. A success code is always returned from this routine.

7.4.2.7 `IMFS_stat()` for Regular Files**Corresponding Structure Element:**`IMFS_stat()`**Arguments:**

```
1 rtems_filesystem_location_info_t *loc,
2 struct stat *buf
```

File:

imfs_stat.c

Description:

This routine actually performs status processing for both devices and regular files.

The `IMFS_jnode_t` structure is referenced to determine the type of node under the filesystem.

If the node is associated with a device, node information is extracted and transformed to set the `st_dev` element of the `stat` structure.

If the node is a regular file, the size of the regular file is extracted from the node.

This routine rejects other node types.

The following information is extracted from the node and placed in the `stat` structure:

- `st_mode`
- `st_nlink`
- `st_ino`
- `st_uid`
- `st_gid`
- `st_atime`
- `st_mtime`
- `st_ctime`

7.4.2.8 IMFS_fchmod() for Regular Files

Corresponding Structure Element:

IMFS_fchmod()

Arguments:

```
1 rtems_libio_t    *iop
2 mode_t          mode
```

File:

imfs_fchmod.c

Description:

This routine will obtain the pointer to the IMFS_jnode_t structure from the information currently in the file control block.

Based on configuration the routine will acquire the user ID from a call to getuid() or from the IMFS_jnode_t structure.

It then checks to see if we have the ownership rights to alter the mode of the file. If the caller does not, an error code is returned.

An additional test is performed to verify that the caller is not trying to alter the nature of the node. If the caller is attempting to alter more than the permissions associated with user group and other, an error is returned.

If all the preconditions are met, the user, group and other fields are set based on the mode calling parameter.

7.4.2.9 memfile_ftruncate() for Regular Files

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.2.10 No pathconf() for Regular Files

Corresponding Structure Element:

NULL

Arguments:

Not Implemented

File:

Not Implemented

Description:

Not Implemented

7.4.2.11 No fsync() for Regular Files

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.2.12 IMFS_fdatasync() for Regular Files

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.3 Directory Handler Table Functions

Handler table functions are defined in a `rtems_filesystem_file_handlers_r` structure. It defines functions that are specific to a node type in a given filesystem. One table exists for each of the filesystem's node types. The structure definition appears below. It is followed by general developmental information on each of the functions associated with directories contained in this function management structure.

```

1 rtems_filesystem_file_handlers_r IMFS_directory_handlers = {
2   IMFS_dir_open,
3   IMFS_dir_close,
4   IMFS_dir_read,
5   NULL,          /* write */
6   NULL,          /* ioctl */
7   IMFS_dir_lseek,
8   IMFS_dir_fstat,
9   IMFS_fchmod,
10  NULL,          /* ftruncate */
11  NULL,          /* fpathconf */
12  NULL,          /* fsync */
13  IMFS_fdatasync,

```

(continues on next page)

(continued from previous page)

```

14     IMFS_fcntl
15 };

```

7.4.3.1 IMFS_dir_open() for Directories

Corresponding Structure Element:

```
imfs_dir_open()
```

Arguments:

```

1 rtems_libio_t *iop,
2 const char    *pathname,
3 unsigned32    flag,
4 unsigned32    mode

```

File:

```
imfs_directory.c
```

Description:

This routine will look into the file control block to find the jnode that is associated with the directory.

The routine will verify that the node is a directory. If its not a directory an error code will be returned.

If it is a directory, the offset in the file control block will be set to 0. This allows us to start reading at the beginning of the directory.

7.4.3.2 IMFS_dir_close() for Directories

Corresponding Structure Element:

```
imfs_dir_close()
```

Arguments:

```

1 rtems_libio_t *iop

```

File:

```
imfs_directory.c
```

Description:

This routine is a dummy for directories under the base filesystem. It immediately returns a success status.

7.4.3.3 IMFS_dir_read() for Directories

Corresponding Structure Element:

imfs_dir_read

Arguments:

```
1 rtems_libio_t *iop,  
2 void          *buffer,  
3 unsigned32    count
```

File:

imfs_directory.c

Description:

This routine will read a fixed number of directory entries from the current directory offset. The number of directory bytes read will be returned from this routine.

7.4.3.4 No write() for Directories

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.3.5 No ioctl() for Directories

Corresponding Structure Element:

ioctl

Arguments:

Not supported

File:

Not supported

Description:

XXX

7.4.3.6 IMFS_dir_lseek() for Directories

Corresponding Structure Element:

imfs_dir_lseek()

Arguments:

```

1 rtems_libio_t      *iop,
2 off_t             offset,
3 int               whence

```

File:

imfs_directory.c

Description:

This routine alters the offset in the file control block.

No test is performed on the number of children under the current open directory. The `imfs_dir_read()` function protects against reads beyond the current size to the directory by returning a 0 bytes transfered to the calling programs whenever the file position index exceeds the last entry in the open directory.

7.4.3.7 IMFS_dir_fstat() for Directories

Corresponding Structure Element:

imfs_dir_fstat()

Arguments:

```

1 rtems_filesystem_location_info_t *loc,
2 struct stat                   *buf

```

File:

imfs_directory.c

Description:

The node access information in the `rtems_filesystem_location_info_t` structure is used to locate the appropriate `IMFS_jnode_t` structure. The following information is taken from the `IMFS_jnode_t` structure and placed in the `stat` structure:

- `st_ino`
- `st_mode`
- `st_nlink`
- `st_uid`
- `st_gid`
- `st_atime`
- `st_mtime`
- `st_ctime`

The `st_size` field is obtained by running through the chain of directory entries and summing the sizes of the `dirent` structures associated with each of the children of the directory.

7.4.3.8 IMFS_fchmod() for Directories

Corresponding Structure Element:

IMFS_fchmod()

Arguments:

```
1 rtems_libio_t    *iop
2 mode_t          mode
```

File:

imfs_fchmod.c

Description:

This routine will obtain the pointer to the `IMFS_jnode_t` structure from the information currently in the file control block.

Based on configuration the routine will acquire the user ID from a call to `getuid()` or from the `IMFS_jnode_t` structure.

It then checks to see if we have the ownership rights to alter the mode of the file. If the caller does not, an error code is returned.

An additional test is performed to verify that the caller is not trying to alter the nature of the node. If the caller is attempting to alter more than the permissions associated with user group and other, an error is returned.

If all the preconditions are met, the user, group and other fields are set based on the mode calling parameter.

7.4.3.9 No ftruncate() for Directories

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.3.10 No fpathconf() for Directories

Corresponding Structure Element:

fpathconf

Arguments:

Not Implemented

File:

Not Implemented

Description:

Not Implemented

7.4.3.11 No fsync() for Directories

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.3.12 IMFS_fdatasync() for Directories

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.4 Device Handler Table Functions

Handler table functions are defined in a `rtems_filesystem_file_handlers_r` structure. It defines functions that are specific to a node type in a given filesystem. One table exists for each of the filesystem's node types. The structure definition appears below. It is followed by general developmental information on each of the functions associated with devices contained in this function management structure.

```

1 typedef struct {
2     rtems_filesystem_open_t      open;
3     rtems_filesystem_close_t    close;

```

(continues on next page)

(continued from previous page)

```

4  rtems_filesystem_read_t      read;
5  rtems_filesystem_write_t    write;
6  rtems_filesystem_ioctl_t    ioctl;
7  rtems_filesystem_lseek_t    lseek;
8  rtems_filesystem_fstat_t    fstat;
9  rtems_filesystem_fchmod_t   fchmod;
10 rtems_filesystem_ftruncate_t ftruncate;
11 rtems_filesystem_fpathconf_t fpathconf;
12 rtems_filesystem_fsync_t    fsync;
13 rtems_filesystem_fdatasync_t fdatasync;
14 } rtems_filesystem_file_handlers_r;

```

7.4.4.1 device_open() for Devices

Corresponding Structure Element:

device_open()

Arguments:

```

1 rtems_libio_t    *iop,
2 const char      *pathname,
3 unsigned32      flag,
4 unsigned32      mode

```

File:

deviceio.c

Description:

This routine will use the file control block to locate the node structure for the device.

It will extract the major and minor device numbers from the jnode.

The major and minor device numbers will be used to make a rtems_io_open() function call to open the device driver. An argument list is sent to the driver that contains the file control block, flags and mode information.

7.4.4.2 device_close() for Devices

Corresponding Structure Element:

device_close()

Arguments:

```

1 rtems_libio_t    *iop

```

File:

deviceio.c

Description:

This routine extracts the major and minor device driver numbers from the `IMFS_jnode_t` that is referenced in the file control block.

It also forms an argument list that contains the file control block.

A `rtems_io_close()` function call is made to close the device specified by the major and minor device numbers.

7.4.4.3 `device_read()` for Devices**Corresponding Structure Element:**

`device_read()`

Arguments:

```

1 rtems_libio_t    *iop,
2 void            *buffer,
3 unsigned32      count
```

File:

`deviceio.c`

Description:

This routine will extract the major and minor numbers for the device from the - jnode- associated with the file descriptor.

A `rtems_io_read()` call will be made to the device driver associated with the file descriptor. The major and minor device number will be sent as arguments as well as an argument list consisting of:

- file control block
- file position index
- buffer pointer where the data read is to be placed
- count indicating the number of bytes that the program wishes to read from the device
- flags from the file control block

On return from the `rtems_io_read()` the number of bytes that were actually read will be returned to the calling program.

7.4.4.4 `device_write()` for Devices**Corresponding Structure Element:**

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.4.5 device_ioctl() for Devices

Corresponding Structure Element:

ioctl

Arguments:

```

1 rtems_libio_t      *iop,
2 unsigned32         command,
3 void               *buffer

```

File:

deviceio.c

Description:

This handler will obtain status information about a device.

The form of status is device dependent.

The rtems_io_control() function uses the major and minor number of the device to obtain the status information.

rtems_io_control() requires an rtems_libio_ioctl_args_t argument list which contains the file control block, device specific command and a buffer pointer to return the device status information.

The device specific command should indicate the nature of the information that is desired from the device.

After the rtems_io_control() is processed, the buffer should contain the requested device information.

If the device information is not obtained properly a -1 will be returned to the calling program, otherwise the ioctl_return value is returned.

7.4.4.6 device_lseek() for Devices

Corresponding Structure Element:

device_lseek()

Arguments:

```

1 rtems_libio_t      *iop,
2 off_t              offset,
3 int                 whence

```

File:

deviceio.c

Description:

At the present time this is a placeholder function. It always returns a successful status.

7.4.4.7 IMFS_stat() for Devices

Corresponding Structure Element:

IMFS_stat()

Arguments:

```

1 rtems_filesystem_location_info_t *loc,
2 struct stat *buf

```

File:

imfs_stat.c

Description:

This routine actually performs status processing for both devices and regular files.

The IMFS_jnode_t structure is referenced to determine the type of node under the filesystem.

If the node is associated with a device, node information is extracted and transformed to set the st_dev element of the stat structure.

If the node is a regular file, the size of the regular file is extracted from the node.

This routine rejects other node types.

The following information is extracted from the node and placed in the stat structure:

- st_mode
- st_nlink
- st_ino
- st_uid
- st_gid
- st_atime
- st_mtime
- st_ctime

7.4.4.8 IMFS_fchmod() for Devices

Corresponding Structure Element:

IMFS_fchmod()

Arguments:

```

1 rtems_libio_t *iop
2 mode_t mode

```

File:

imfs_fchmod.c

Description:

This routine will obtain the pointer to the `IMFS_jnode_t` structure from the information currently in the file control block.

Based on configuration the routine will acquire the user ID from a call to `getuid()` or from the `IMFS_jnode_t` structure.

It then checks to see if we have the ownership rights to alter the mode of the file. If the caller does not, an error code is returned.

An additional test is performed to verify that the caller is not trying to alter the nature of the node. If the caller is attempting to alter more than the permissions associated with user group and other, an error is returned.

If all the preconditions are met, the user, group and other fields are set based on the mode calling parameter.

7.4.4.9 No `ftruncate()` for Devices

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.4.10 No `fpathconf()` for Devices

Corresponding Structure Element:

`fpathconf`

Arguments:

Not Implemented

File:

Not Implemented

Description:

Not Implemented

7.4.4.11 No `fsync()` for Devices

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

7.4.4.12 No fdatsync() for Devices

Not Implemented

Corresponding Structure Element:

XXX

Arguments:

XXX

File:

XXX

Description:

XXX

MINIATURE IN-MEMORY FILESYSTEM

This chapter describes the Miniature In-Memory FileSystem (miniIMFS). The miniIMFS is a reduced feature version of the IMFS designed to provide minimal functionality and have a low memory footprint.

This chapter should be written after the IMFS chapter is completed and describe the implementation of the mini-IMFS.

TRIVIAL FTP CLIENT FILESYSTEM

This chapter describes the Trivial File Transfer Protocol (TFTP) Client Filesystem. TFTP is designed to be an especially simple protocol which uses the User Datagram Protocol (UDP) for data transfer over the Internet. Its purpose is to send a single file between to network nodes (client and server). A file can be sent in both directions, i.e. a client can either read a file from a server or write a file to the server.

Besides reading or writing a file no other operations are supported. That is, one cannot seek the file, not append to the end of a file, not open the file for reading and writing at the same time, not list directories, not move files and so on.

TFTP is inherent insecure as it does not provide any means for authentication or encryption. Therefore, it is highly recommended not to employ it on public networks. Nevertheless, it is still widely used to load software and configuration data during early boot stages over a Local Area Network (LAN).

9.1 RTEMS TFTP Filesystem Implementation

The RTEMS TFTP filesystem implements a TFTP client which can be used through the file system. With other words, one needs to mount the TFTP filesystem and can afterwards open a file for reading or writing below that mount point. The content of that file is then effectively read from or written to the remote server. The RTEMS implementation implements the following features:

- [RFC 1350](#) *The TFTP Protocol (Revision 2)*
- [RFC 2347](#) *TFTP Option Extension*
- [RFC 2348](#) *TFTP Blocksize Option*
- [RFC 7440](#) *TFTP Windowsize Option*

Many simple TFTP server do not support options (RFC 2347). Therefore, in case the server rejects the first request with options, the RTEMS client makes automatically a second attempt using only the “classical” RFC 1350.

The implementation has the following shortcomings:

- IPv6 is not supported (yet).
- No congestion control is implemented.

(Congestion is simply expressed a network traffic jam which involves package loss.) This implementation would worsen a congestion situation and squeeze out TCP connections. If that is a concern in your setup, it can be prevented by using value *1* as *windowsize* when mounting the TFTP file system.

- One must call `open()`, `read()`, `write()` and `close()` at a good pace.

TFTP is designed to read or write a whole already existing file in one sweep. It uses timeouts (of unspecified length) and it does not know keep-alive messages. If the client does not respond to the server in due time, the server sets the connection faulty and drops it. To avoid this, the user must read or write enough data fast enough.

The point here is, one cannot pause the reading or writing for longer periods of time. TFTP cannot be used for example to write log files where all few seconds a line is written. Also opening the file at the beginning of an application and closing it that the end will certainly lead to a timeout. As another example, one cannot read a file by reading one byte per second, this will trigger a timeout and the server closes the connection. The opening, reading or writing and closing must happen in swift consecutive steps.

- The transfer mode is always `octet`. The only alternative `netascii` cannot be selected.
- Block number roll-over is currently not supported. Therefore, the maximum file size is limited to `max-block-number` times `blocksize`. For RFC 1350 `blocksize` is would be $65535 * 512 = 32$ MB. For the default `blocksize` is would be $65535 * 1456 = 90$ MB.
- The inherent insecurity of the protocol has already be mentioned but it is worth repeating.

9.2 Prerequisites

To use the RTEMS TFTP filesystem one needs:

- The RTEMS tools (cross-compiler, linker, debugger etc.)
- The RTEMS Board Support Package (BSP)
- A network stack for RTEMS, for example RTEMS libbsd

As an example the ARM architecture and a `xilinx_zynq_a9` BSP is used below together with RTEMS libbsd. The instructions are tested with RTEMS version 6. It is recommended to actually use `arm/xilinx_zynq_a9_qemu` for the first experiments as other BSPs tend to require different configuration values and/or command line options.

Moreover, it is recommended to first execute any code using QEMU as simulator so that no hardware is needed. Therefore, `qemu-system-arm` must be installed. In Linux distributions this executable is usually available in the repositories as package `qemu-arm`.

9.2.1 RTEMS Tools

Instructions on how to obtain, compile and install the RTEMS tools can be found in the *RTEMS User Manual* chapter 2. *Quick Start*. To follow the suggested example `6/rtems-arm` should be used as target architecture argument of the `../source-builder/sb-set-builder` command.

9.2.2 RTEMS Board Support Package

Instructions on how to obtain, compile and install a BSP can be found in the *RTEMS User Manual* section *Build a Board Support Package (BSP)*. The `bsp`-option should have the following value to match the example BSP:

```
1 --rtems-bsps=arm/xilinx_zynq_a9_qemu
```

9.2.3 RTEMS libbsd

Instructions on how to obtain, compile and install RTEMS libbsd can be found in the `README.rst` of the `rtems-libbsd` [GIT repository](#). Make sure to compile and install libbsd for the correct RTEMS version (here 6). The default build set (`--buildset=buildset/default.ini`) does suffice and as BSP `--rtems-bsp=arm/xilinx_zynq_a9_qemu` is to be used with the `waf configure` command.

9.2.4 RTEMS Configuration

To make the TFTP filesystem available to an RTEMS application and have it initialized, the macro `CONFIGURE_FILESYSTEM_TFTPFS` must be defined when configuring RTEMS (typically in the `init.c` file):

```
1 #define CONFIGURE_FILESYSTEM_TFTPFS
```

Moreover, libbsd and RTEMS must be configured appropriately as well. For orientation, the code below is from an application using TFTP FS (file `tftp_init.c`).

```

1 /* Configure libbsd. */
2 #define RTEMS_BSD_CONFIG_NET_PF_UNIX
3 #define RTEMS_BSD_CONFIG_NET_IF_BRIDGE
4 #define RTEMS_BSD_CONFIG_NET_IF_LAGG
5 #define RTEMS_BSD_CONFIG_NET_IF_VLAN
6 #define RTEMS_BSD_CONFIG_BSP_CONFIG
7 #define RTEMS_BSD_CONFIG_INIT
8
9 #include <machine/rtems-bsd-config.h>
10
11 /* RTEMS configuration for libbsd */
12 #define CONFIGURE_MAXIMUM_USER_EXTENSIONS 1
13 #define CONFIGURE_INIT_TASK_STACK_SIZE (32 * 1024)
14 #define CONFIGURE_INIT_TASK_INITIAL_MODES RTEMS_DEFAULT_MODES
15 #define CONFIGURE_INIT_TASK_ATTRIBUTES RTEMS_FLOATING_POINT
16 #define CONFIGURE_APPLICATION_NEEDS_LIBBLOCK
17
18 /* RTEMS configuration for tftp */
19 #define CONFIGURE_FILESYSTEM_TFTPFS
20 #define CONFIGURE_MAXIMUM_FILE_DESCRIPTOR 64
21
22 /* Simple RTEMS configuration */
23 #define CONFIGURE_APPLICATION_NEEDS_CLOCK_DRIVER
24 #define CONFIGURE_APPLICATION_NEEDS_CONSOLE_DRIVER
25 #define CONFIGURE_UNLIMITED_OBJECTS
26 #define CONFIGURE_UNIFIED_WORK_AREAS
27 #define CONFIGURE_RTEMS_INIT_TASKS_TABLE
28 #define CONFIGURE_INIT
29
30 #include <rtems/confdefs.h>

```

9.2.5 Application Linkage

The TFTP filesystem is compiled and linked into `libtftpfs`. After installation it should be in a place like:

```
1 <PREFIX>/arm-rtems6/xilinx_zynq_a9_qemu/lib/libtftpfs.a
```

An RTEMS application which wants to use the TFTP filesystem must be linked with the libraries `libtftpfs`, `libbsd`, and `libm` — in this order. An example build target in a `wscript` for use with the RTEMS WAF build system could be:

```

1 def build(ctx):
2     rtems.build(ctx)
3     ctx(features = 'c cprogram',
4         target = 'tftp_app.exe',
5         cflags = '-g -O2',
6         source = ['tftp_app.c', 'tftp_init.c'],
7         lib     = ['tftpfs', 'bsd', 'm'])

```

9.2.6 Network Configuration and TFTP Server

QEMU has a simple build-in TFTP server which can serve files for reading only. By default it is reachable from the application executed by QEMU at IP address `10.0.2.2` if SLIRP networking is used. For the example `arm/xilinx_zynq_a9_qemu` BSP, the QEMU option

```
1 -nic user,model=cadence_gem,tftp=/tmp
```

will cause this TFTP server to deliver files found below directory `/tmp`. Note that SLIRP requires that the application uses DHCP.

Alternatively, it is of course possible to use other kinds of QEMU networking (as for example the TAP virtual Ethernet interface described in the above mentioned `README.rst` in section *Qemu and Networking*). Also an external TFTP server can be used.

9.2.7 External TFTP Server Example for OpenSUSE

This example uses `atftp` as an external TFTP server to which the RTEMS TFTP file system running in an QEMU instance connects to. `atftp` was compiled from the sources. Instructions how to compile and install `atftp` can be found in the `INSTALL` file which comes with its sources.

On an OpenSUSE 15.3 machine, the following commands sets up `atftp` for use with the mentioned TAP interface (these commands must be executed as root; `<APP-USER>` must be replaced by the name of the “normal” user starting the RTEMS application in QEMU later on; for other distributions the `firewall-cmd` commands must be replaced by the equivalent of that distribution):

```
1 # Create and configure TAP interface
2 ip tuntap add qtap mode tap user <APP-USER>
3 ip link set dev qtap up
4 ip addr add 169.254.1.1/16 dev qtap
5
6 # Open firewalld as non-permanent configuration
7 firewall-cmd --zone=home --add-service=tftp
8 firewall-cmd --zone=home --add-interface=qtap
9
10 # Start TFTP daemon
11 touch /var/log/atftpd/atftp.log
12 chown tftp.tftp /var/log/atftpd/atftp.log
13 atftpd --user tftp --group tftp --daemon --verbose \
14     --logfile /var/log/atftpd/atftp.log /srv/tftpboot
```

The `atftp` server will then be reachable from an application executed by QEMU at the address of the TAP interface which is in this case `169.254.1.1`. When used with this TAP interface, the QEMU network option must be changed to (replacing the `-net` options in the examples found in the already mentioned `README.rst` of the `rtems-libbsd` GIT repository):

```
1 -nic tap,model=cadence_gem,ifname=qtap,script=no,downscript=no
```

9.3 Usage

The following diagram *usage* (page 105) shows how the TFTP filesystem is used by an application. The mount point can be any directory. The name `/tftp` used in the figure serves only as an example. The final unmounting and remove directory steps are optional.

9.3.1 Mounting the TFTP Filesystem

When mounting the TFTP filesystem, the argument `filesystemtype` must be `RTEMS_FILESYSTEM_TYPE_TFTPFS` (`#include <rtems/libio.h>`).

The argument `data` can either be

- a 0-terminated C string of comma separated mount options or
- `NULL` for mounting with default values.

The mount options are case sensitive. Spaces are not allowed in the string. If conflicting options are specified, the ones more to the right (i.e. end of the string) take precedence. These mount options are supported:

blocksize=N

where `N` is a decimal integer number.

The TFTP `blocksize` option is introduced in RFC 2348. It defines the number of octets in the data packages transferred. Valid values range between 8 and 65464 octets, inclusive. Values larger than 1468 may cause package fragmentation over standard Ethernet. A value of 512 will prevent this option from being sent to the server.

The default value is 1456.

windowsize=N

where `N` is a decimal integer number.

The TFTP `windowsize` option is introduced in RFC 7440. It defines the number of data packages send before the receiver must send an acknowledgment package. Valid values range between 1 and 65535 packages, inclusive. Simple TFTP servers usually do not support this option. This option may negatively contribute to network congestion. This can be avoided by using a window size of 1. A value of 1 will prevent this option from being sent to the server.

The default value is 8.

rfc1350

The TFTP client should strictly follow RFC 1350 and not send any options to the server. Many simple TFTP server do still not support the option extension defined in RFC 2347. The TFTP filesystem will always make a second option-less connection attempt to the TFTP server in case a first attempt with options was rejected with an error message.

This option is equivalent to `blocksize=512,windowsize=1`.

verbose

During operation, print messages to `stdout`. This option has currently little effect. It is kept to be compatible to older implementations.




Fig. 9.1: TFTP file system usage

9.3.2 Opening a File

Files must be opened by using either `O_RDONLY` or `O_WRONLY` as flags but not both. Other flags are not supported.

The pathname argument to `open()` has the following format:

```
1 <PREFIX>/<server-address>:<path-on-server>
```

<PREFIX>

The path to the point where the TFTP filesystem is mounted. This can be a relative path from the current working directory or an absolute path.

<server-address>

The network address for the TFTP server from which to download the file or to which the file should be sent. This is either

- an IPv4 address (like *127.0.0.1*) or
- the (full-qualified) name of an IPv4 host (acceptable to `gethostbyname()`)

The port number cannot be specified and will always be the one reserved for TFTP: 69.

<path-on-server>

The path and file name at which the TFTP server will find or create the file. Any directories in this path must already exist. It is not possible to create or read directories with TFTP. RFC 1350 specifies that this `<path-on-server>` must be in *netascii*:

This is *ascii* as defined in “USA Standard Code for Information Interchange” [1] with the modifications specified in “Telnet Protocol Specification” [3].

[1] USA Standard Code for Information Interchange, USASI X3.4-1968.

[3] Postel, J., “Telnet Protocol Specification,” RFC 764, USC/Information Sciences Institute, June, 1980.

Example pathnames:

```
1 "/tftp/169.254.1.1:file.txt"
2 "/TFTPFS/tftp-server.sample.org:bootfiles/image"
```

In the above examples, `/tftp` and `/TFTPFS` are the directory at which the TFTP filesystem is mounted. `169.254.1.1` and `tftp-server.sample.org` are the network address of the TFTP server to contact. `file.txt` and `bootfiles/image` are the file name and the path at the server side.

9.3.3 Closing a File

Especially, when writing a file to the server, the return code of `close()` should be checked. Invoking `close()` triggers the sending of the last – not completely filled – data block. This may fail the same way as any `write()` may fail. Therefore, an error returned by `close()` likely indicates that the file was not completely transferred.

9.4 Use From Shell

It is possible to use the RTEMS shell through test `media01` of `libbsd` to exercise the TFTP filesystem. This text assumes that `libbsd` has already been setup, configured, compiled and installed as described in the `README.rst` of the `rtems-libbsd` GIT repository. How the test `media01.exe` can be executed is described in section *Qemu and Networking* of that file.

A TFTP server must be setup and run. The instructions to setup an TAP device and an `atftp` server found above in section *External TFTP Server Example for OpenSUSE* (page 103) could be followed for this purpose. It may be useful to create a sample file for later download in the directory served by the TFTP server. For `atftp` “root” could create a file with these instructions:

```
1 # echo "Hello World!" >/srv/tftpboot/hello.txt
2 # chown tftp.tftp /srv/tftpboot/hello.txt
```

Start the `media01` test in one terminal — as “normal” user:

```
1 $ qemu-system-arm -serial null -serial mon:stdio -nographic \
2 -M xilinx-zynq-a9 -m 256M \
3 -nic tap,model=cadence_gem,ifname=qtap,script=no,downscript=no \
4 -kernel build/arm-rtems6-xilinx_zynq_a9_qemu-default/media01.exe
```

Wait till a line like the following is printed in the terminal:

```
1 info: cgem0: using IPv4LL address 169.254.191.13
```

Next use the displayed IP address to open a telnet connection in a second terminal:

```
1 $ telnet 169.254.191.13
```

At the telnet prompt, enter this command to list the filesystems available for mounting:

```
1 TLNT [/] # mount -L
2 File systems: / dosfs tftpfs
```

`tftpfs` should be among them. Create a directory and mount the TFTP filesystem:

```
1 TLNT [/] # mkdir /tftp
2 TLNT [/] # mount -t tftpfs -o verbose "" /tftp
3 mounted -> /tftp
```

Now, files can be sent to and read from the TFTP server using the usual shell commands:

```
1 TLNT [/] # cp /etc/dhcpd.duid /tftp/169.254.1.1:dhcpd.duid
2 TFTPFS: /169.254.1.1:dhcpd.duid
3 TLNT [/] # cat /tftp/169.254.1.1:hello.txt
4 TFTPFS: /169.254.1.1:hello.txt
5 Hello World!
```

The terminal session can be terminated with key combination “CTRL-]” followed by a quit command; the QEMU simulation with “CTRL-a x” and `tail -f` with “CTRL-c”.

9.5 TFTP Client API

The TFTP filesystem has a TFTP client which is responsible to handle all network traffic. It permits the use of TFTP without filesystem. Essentially, one saves the mounting of the filesystem. Otherwise the usage is similar to the one of the filesystem. The equivalent of the `open()`, `read()`, `write()`, and `close()` functions are:

```
1 int tftp_open(  
2     const char *hostname,  
3     const char *path,  
4     bool is_for_reading,  
5     const tftp_net_config *config,  
6     void **tftp_handle  
7 );  
8  
9 ssize_t tftp_read( void *tftp_handle, void *buffer, size_t count );  
10  
11 ssize_t tftp_write( void *tftp_handle, const void *buffer, size_t count );  
12  
13 int tftp_close( void *tftp_handle );
```

`tftp_open()` accepts as input a data structure of type `tftp_net_config`. It can be used to specify certain values governing the file transfer such as the already described options. Data of `tftp_net_config` type can be initialized using function

```
1 void tftp_initialize_net_config( tftp_net_config *config );
```

The full description can be found in the file `cpukit/include/rtems/tftp.h`. The function `rtems_tftpfs_initialize()` found there is only for RTEMS internal use by the `mount()` function.

9.6 Software Design

The original source code contained only the files `cpukit/include/rtems/tftp.h` and `cpukit/libfs/src/ftpfs/tftpDriver.c`. There was no test suite nor any documentation.

When the code was extended to support options (RFC 2347 and others), the code in `tftpDriver.c` was split. The new file `tftpfs.c` is responsible to handle all filesystem related issues while `tftpDriver.c` provides the network related functions. In effect `tftpDriver.c` is a TFTP client library which can be used independently of the filesystem. `tftpfs.c` calls the functions of `tftpDriver.c` to do the actual TFTP file transfer.

At this occasion a test suite and this documentation in the *RTEMS Filesystem Design Guide* was added.

9.6.1 Test Suite

The TFTP filesystem comes with an extensive test suite.

`libtftpfs` source code is situated in the RTEMS repository. For testing it, either `libbsd` or RTEMS legacy networking would have been required. This implies that the tests for `libtftpfs` would have needed to be placed in the `libbsd` repository — a different one than the `libtftpfs` source code.

Yet, `libtftpfs` uses only a handful of networking functions. The test suite provides fake implementations of those functions. These fake functions permit to simulate the exchange of UDP packages with the `libtftpfs` code and thus permits testing the TFTP filesystem without the need of a full network stack.

Consequently, the test suite is placed in the RTEMS repository together with the TFTP filesystem source code. Neither `libbsd` nor RTEMS legacy networking is required to run the tests.

The test suite can be executed using the `rtems-test` tool:

```
1 $ cd <path-to-rtems-git-worktree>
2 $ rtems-test --log-mode=all --rtems-bsp=xilinx_zynq_a9_qemu \
3   build/arm/xilinx_zynq_a9_qemu/testsuites/fstests/tftpfs.exe
```


COMMAND AND VARIABLE INDEX

There are currently no Command and Variable Index entries.